

# AMD Core Math Library (ACML)

---

Version 3.1.0

Copyright © 2003-2006 Advanced Micro Devices, Inc., Numerical Algorithms Group Ltd.

---

AMD, the AMD Arrow logo, AMD Opteron, AMD Athlon and combinations thereof are trademarks of Advanced Micro Devices, Inc.

## Short Contents

1	Introduction . . . . .	1
2	General Information . . . . .	3
3	BLAS: Basic Linear Algebra Subprograms . . . . .	16
4	LAPACK: Package of Linear Algebra Subroutines . . . . .	17
5	Fast Fourier Transforms (FFTs) . . . . .	21
6	Random Number Generators . . . . .	65
7	ACML-MV: Fast Math and Fast Vector Math Library . . . .	154
8	References . . . . .	215
	Subject Index . . . . .	216
	Routine Index . . . . .	219

# Table of Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>General Information</b>	<b>3</b>
2.1	Determining the best ACML version for your system	3
2.2	Accessing the Library (Linux)	5
2.2.1	Accessing the Library under Linux using GNU g77/gcc	5
2.2.2	Accessing the Library under Linux using GNU gfortran/gcc	6
2.2.3	Accessing the Library under Linux using PGI compilers pgf77/pgf90/pgcc	6
2.2.4	Accessing the Library under Linux using PathScale compilers pathf90/pathcc	7
2.2.5	Accessing the Library under Linux using compilers other than GNU, PGI or PathScale	8
2.3	Accessing the Library (Microsoft Windows)	8
2.3.1	Accessing the Library under 32-bit Windows using GNU g77/gcc	8
2.3.2	Accessing the Library under 32-bit Windows using PGI compilers pgf77/pgf90/pgcc	9
2.3.3	Accessing the Library under 32-bit Windows using Microsoft C or Intel Fortran	10
2.3.4	Accessing the Library under 32-bit Windows using the Compaq Visual Fortran compiler	10
2.3.5	Accessing the Library under 32-bit Windows using the Salford FTN95 compiler	11
2.3.6	Accessing the Library under 64-bit Windows	11
2.4	Accessing the Library (Solaris)	12
2.4.1	Accessing the Library under Solaris	12
2.5	ACML FORTRAN and C interfaces	13
2.6	Library Version and Build Information	14
2.7	Library Documentation	15
2.8	Example programs calling ACML	15
<b>3</b>	<b>BLAS: Basic Linear Algebra Subprograms</b>	<b>16</b>
<b>4</b>	<b>LAPACK: Package of Linear Algebra Subroutines</b>	<b>17</b>
4.1	Introduction to LAPACK	17
4.2	Reference sources for LAPACK	17
4.3	LAPACK block sizes, ILAENV and ILAENVSET	18

<b>5</b>	<b>Fast Fourier Transforms (FFTs) .....</b>	<b>21</b>
5.1	Introduction to FFTs .....	21
5.1.1	Transform definitions and Storage for Complex Data .....	21
5.1.2	Transform definitions and Storage for Real Data .....	22
5.1.3	Efficiency .....	22
5.1.4	Default and Generated Plans .....	23
5.2	FFTs on Complex Sequences .....	24
5.2.1	FFT of a single sequence .....	24
	ZFFT1D Routine Documentation .....	25
	CFFT1D Routine Documentation .....	26
	ZFFT1DX Routine Documentation .....	27
	CFFT1DX Routine Documentation .....	29
5.2.2	FFT of multiple complex sequences .....	31
	ZFFT1M Routine Documentation .....	32
	CFFT1M Routine Documentation .....	34
	ZFFT1MX Routine Documentation .....	36
	CFFT1MX Routine Documentation .....	38
5.2.3	2D FFT of two-dimensional arrays of data .....	40
	ZFFT2D Routine Documentation .....	41
	CFFT2D Routine Documentation .....	42
	ZFFT2DX Routine Documentation .....	43
	CFFT2DX Routine Documentation .....	46
5.2.4	3D FFT of three-dimensional arrays of data .....	49
	ZFFT3D Routine Documentation .....	50
	CFFT3D Routine Documentation .....	51
	ZFFT3DX Routine Documentation .....	52
	CFFT3DX Routine Documentation .....	54
5.3	FFTs on real and Hermitian data sequences .....	56
5.3.1	FFT of single sequences of real data .....	57
	DZFFT Routine Documentation .....	57
	SCFFT Routine Documentation .....	58
5.3.2	FFT of multiple sequences of real data .....	59
	DZFFTM Routine Documentation .....	59
	SCFFTM Routine Documentation .....	60
5.3.3	FFT of single Hermitian sequences .....	61
	ZDFFT Routine Documentation .....	61
	CSFFT Routine Documentation .....	62
5.3.4	FFT of multiple Hermitian sequences .....	63
	ZDFFTM Routine Documentation .....	63
	CSFFTM Routine Documentation .....	64

<b>6</b>	<b>Random Number Generators .....</b>	<b>65</b>
6.1	Base Generators .....	65
6.1.1	Initialization of the Base Generators .....	66
	DRANDINITIALIZE / SRANDINITIALIZE .....	67
	DRANDINITIALIZEBBS / SRANDINITIALIZEBBS .....	70
6.1.2	Calling the Base Generators .....	71
	DRANDBLUMBLUMSHUB / SRANDBLUMBLUMSHUB .....	72
6.1.3	Basic NAG Generator .....	72
6.1.4	Wichmann-Hill Generator .....	73
6.1.5	Mersenne Twister .....	73
6.1.6	L'Ecuyer's Combined Recursive Generator .....	74
6.1.7	Blum-Blum-Shub Generator .....	74
6.1.8	User Supplied Generators .....	75
	DRANDINITIALIZEUSER / SRANDINITIALIZEUSER .....	76
	UNINI .....	78
	UGEN .....	79
6.2	Multiple Streams .....	79
6.2.1	Using Different Seeds .....	80
6.2.2	Using Different Generators .....	80
6.2.3	Skip Ahead .....	80
	DRANDSKIPHEAD / SRANDSKIPHEAD .....	82
6.2.4	Leap Frogging .....	83
	DRANDLEAPFROG / SRANDLEAPFROG .....	85
6.3	Distribution Generators .....	86
6.3.1	Continuous Univariate Distributions .....	87
	DRANDBETA / SRANDBETA .....	87
	DRANDCAUCHY / SRANDCAUCHY .....	89
	DRANDCHISQUARED / SRANDCHISQUARED .....	91
	DRANDEXPONENTIAL / SRANDEXPONENTIAL .....	93
	DRANDF / SRANDF .....	95
	DRANDGAMMA / SRANDGAMMA .....	97
	DRANDGAUSSIAN / DRANDGAUSSIAN .....	99
	DRANDLOGISTIC / SRANDLOGISTIC .....	101
	DRANDLOGNORMAL / SRANDLOGNORMAL .....	103
	DRANDSTUDENTST / SRANDSTUDENTST .....	105
	DRANDTRIANGULAR / SRANDTRIANGULAR .....	107
	DRANDUNIFORM / SRANDUNIFORM .....	109
	DRANDVONMISES / SRANDVONMISES .....	111
	DRANDWEIBULL / SRANDWEIBULL .....	113
6.3.2	Discrete Univariate Distributions .....	115
	DRANDBINOMIAL / SRANDBINOMIAL .....	115
	DRANDGEOMETRIC / SRANDGEOMETRIC .....	117
	DRANDHYPERGEOMETRIC / SRANDHYPERGEOMETRIC .....	119
	DRANDNEGATIVEBINOMIAL / SRANDNEGATIVEBINOMIAL .....	121
	DRANDPOISSON / SRANDPOISSON .....	123
	DRANDDISCRETEUNIFORM / SRANDDISCRETEUNIFORM .....	125
	DRANDGENERALDISCRETE / SRANDGENERALDISCRETE .....	127
	DRANDBINOMIALREFERENCE / SRANDBINOMIALREFERENCE .....	129

DRANDGEOMETRICREFERENCE / SRANDGEOMETRICREFERENCE ...	131
DRANDHYPERGEOMETRICREFERENCE /	
SRANDHYPERGEOMETRICREFERENCE .....	133
DRANDNEGATIVEBINOMIALREFERENCE /	
SRANDNEGATIVEBINOMIALREFERENCE .....	135
DRANDPOISSONREFERENCE / SRANDPOISSONREFERENCE .....	137
6.3.3 Continuous Multivariate Distributions .....	139
DRANDMULTINORMAL / SRANDMULTINORMAL .....	139
DRANDMULTISTUDENTST / SRANDMULTISTUDENTST .....	141
DRANDMULTINORMALR / SRANDMULTINORMALR .....	144
DRANDMULTISTUDENTSTR / SRANDMULTISTUDENTSTR .....	146
DRANDMULTINORMALREFERENCE / SRANDMULTINORMALREFERENCE	
.....	148
DRANDMULTISTUDENTSTREFERENCE /	
SRANDMULTISTUDENTSTREFERENCE .....	150
6.3.4 Discrete Multivariate Distributions .....	152
DRANDMULTINOMIAL / SRANDMULTINOMIAL .....	152
<b>7 ACML_MV: Fast Math and Fast Vector Math</b>	
<b>Library .....</b>	<b>154</b>
7.1 Introduction to ACML_MV .....	154
7.1.1 Terminology .....	154
7.1.2 Weak Aliases .....	154
7.1.3 Defined Types .....	155
7.2 Fast Basic Math Functions .....	156
<b>fastcos</b> : fast double precision Cosine .....	156
<b>fastcosf</b> : fast single precision Cosine .....	157
<b>fastexp</b> : fast double precision exponential function .....	158
<b>fastexpf</b> : fast single precision exponential function .....	159
<b>fastlog</b> : fast double precision natural logarithm function .....	160
<b>fastlogf</b> : fast single precision natural logarithm function .....	161
<b>fastlog10</b> : fast double precision base-10 logarithm function .....	162
<b>fastlog10f</b> : fast single precision base-10 logarithm function .....	163
<b>fastpow</b> : fast double precision power function .....	164
<b>fastpowf</b> : fast single precision power function .....	166
<b>fastsin</b> : fast double precision Sine .....	168
<b>fastsinf</b> : fast single precision Sine .....	169
<b>fastsincos</b> : fast double precision Sine and Cosine .....	170
<b>fastsincosf</b> : fast single precision Sine and Cosine .....	171
7.3 Fast Vector Math Functions .....	172
<b>vrda_cos</b> : Two-valued double precision Cosine .....	172
<b>vrda_cosf</b> : Four-valued double precision Cosine .....	173
<b>vrda_cos</b> : Array double precision Cosine .....	174
<b>vrda_cosf</b> : Four-valued single precision Cosine .....	175
<b>vrda_cosf</b> : Array single precision Cosine .....	176
<b>vrda_exp</b> : Two-valued double precision exponential function ...	177
<b>vrda_exp</b> : Four-valued double precision exponential function ...	178
<b>vrda_exp</b> : Array double precision exponential function .....	179

<b>vrs4_expf</b> : Four-valued single precision exponential function . . . .	180
<b>vrs8_expf</b> : Eight-valued single precision exponential function . . .	181
<b>vrsa_expf</b> : Array single precision exponential function . . . . .	182
<b>vrda_log</b> : Two-valued double precision natural logarithm . . . . .	183
<b>vrda_log</b> : Four-valued double precision natural logarithm . . . . .	184
<b>vrda_log</b> : Array double precision natural logarithm . . . . .	185
<b>vrs4_logf</b> : Four-valued single precision natural logarithm . . . . .	187
<b>vrs8_logf</b> : Eight-valued single precision natural logarithm . . . . .	188
<b>vrsa_logf</b> : Array single precision natural logarithm . . . . .	189
<b>vrda_log10</b> : Two-valued double precision base-10 logarithm . . . .	190
<b>vrda_log10</b> : Four-valued double precision base-10 logarithm . . . .	191
<b>vrda_log10</b> : Array double precision base-10 logarithm . . . . .	193
<b>vrs4_log10f</b> : Four-valued single precision base-10 logarithm . . . .	195
<b>vrs8_log10f</b> : Eight-valued single precision base-10 logarithm . . . .	196
<b>vrsa_log10f</b> : Array single precision base-10 logarithm . . . . .	198
<b>vrs4_powf</b> : Four-valued single precision power function . . . . .	200
<b>vrs4_powxf</b> : Four-valued single precision power function with constant y . . . . .	202
<b>vrda_sin</b> : Two-valued double precision Sine . . . . .	204
<b>vrda_sin</b> : Four-valued double precision Sine . . . . .	205
<b>vrda_sin</b> : Array double precision Sine . . . . .	206
<b>vrs4_sinf</b> : Four-valued single precision Sine . . . . .	207
<b>vrsa_sinf</b> : Array single precision Sine . . . . .	208
<b>vrda_sincos</b> : Two-valued double precision Sine and Cosine . . . . .	209
<b>vrda_sincos</b> : Array double precision Sine and Cosine . . . . .	210
<b>vrs4_sincosf</b> : Four-valued single precision Sine and Cosine . . . . .	212
<b>vrsa_sincosf</b> : Array single precision Sine and Cosine . . . . .	213
 <b>8 References</b> . . . . .	 <b>215</b>
 <b>Subject Index</b> . . . . .	 <b>216</b>
 <b>Routine Index</b> . . . . .	 <b>219</b>

# 1 Introduction

The AMD Core Math Library (ACML) is a set of numerical routines tuned specifically for AMD64 platform processors (including Opteron™ and Athlon™64 ). The routines, which are available via both FORTRAN 77 and C interfaces, include:

- BLAS - Basic Linear Algebra Subprograms (including Sparse Level 1 BLAS);
- LAPACK - A comprehensive package of higher level linear algebra routines;
- FFT - a set of Fast Fourier Transform routines for real and complex data;
- RNG - a set of random number generators and statistical distribution functions.

The BLAS and LAPACK routines provide a portable and standard set of interfaces for common numerical linear algebra operations that allow code containing calls to these routines to be readily ported across platforms. Full documentation for the BLAS and LAPACK are available online. This manual will, therefore, be restricted to providing brief descriptions of the BLAS and LAPACK and providing links to their documentation and other materials (see [Chapter 3 \[The BLAS\], page 16](#) and see [Chapter 4 \[LAPACK\], page 17](#)).

The FFT is an implementation of the Discrete Fourier Transform (DFT) that makes use of symmetries in the definition to reduce the number of operations required from  $O(n^2)$  to  $O(n \log n)$  when the sequence length,  $n$ , is the product of small prime factors; in particular, when  $n$  is a power of 2. Despite the popularity and widespread use of FFT algorithms, the definition of the DFT is not sufficiently precise to prescribe either the forward and backward directions (these are sometimes interchanged), or the scaling factor associated with the forward and backward transforms (the combined forward and backward transforms may only reproduce the original sequence by following a prescribed scaling).

Currently, there is no agreed standard API for FFT routines. Hardware vendors usually provide a set of high performance FFTs optimized for their systems: no two vendors employ the same interfaces for their FFT routines. The ACML provides a set of FFT routines, optimized for AMD64 processors, using an ACML-specific set of interfaces. The functionality, interfaces and use of the ACML FFT routines are described below (see [Chapter 5 \[Fast Fourier Transforms\], page 21](#)).

The RNG is a comprehensive set of statistical distribution functions which are founded on various underlying uniform distribution generators (*base generators*) including Wichmann-Hill and an implementation of the Mersenne Twister. In addition there are hooks which allow you to supply your own preferred base generator if it is not already included in ACML. All RNG functionality and interfaces are described below (see [Chapter 6 \[Random Number Generators\], page 65](#)).

[Chapter 2 \[General Information\], page 3](#) provides details on:

- how to link a user program to the ACML;
- FORTRAN and C interfaces to ACML routines;
- how to obtain the ACML version and build information;
- how to access the ACML documentation.

A supplementary library of fast math and fast vector math functions (ACML-MV) is also provided with some 64-bit versions of ACML. Some of the functions included in ACML-MV are not callable from high-level languages, but must be called via assembly language; the



documentation of ACML\_MV (see [Chapter 7 \[Fast Vector Math Library\]](#), page 154) gives details for each individual routine.

## 2 General Information

### 2.1 Determining the best ACML version for your system

ACML comes in versions for 64-bit and 32-bit processors, running both Linux and Microsoft Windows® operating systems. To use the following tables, you will need to know answers to these questions:

- Are you running a 64-bit operating system (on AMD64 hardware such as Opteron or Athlon64)? Or are you running a 32-bit operating system?
- Is the operating system Linux or Microsoft Windows?
- Do you have the GNU compilers (g77/gcc or gfortran/gcc) or compatible compilers (compilers that are interoperable with the GNU compilers) installed?
- Do you have the PGI compilers (pgf77/pgf90/pgcc) installed?
- Do you have the PathScale compilers (pathf90/pathcc) installed?
- On a 32-bit Windows machine, do you have Microsoft C, or Compaq Visual Fortran, or compatible compilers installed?
- Do you have a single processor system or a multiprocessor (SMP) system? The single processor version of ACML can be run on an SMP machine and vice versa, but (if you have the right compilers) it is more efficient to run the version appropriate to the machine.
- If you're on a 32-bit machine, does it support Streaming SIMD Extension instructions (SSE or SSE2)?

The ACML installation includes a binary utility that can help you find an answer to the last question. The utility lies in directory `util`, and is named `cpuid.exe`. It interrogates the processor to determine whether SSE and SSE2 instructions exist.

`util/cpuid.exe`

Under a Linux operating system, another way of finding out the answer to the last question is to look at the special file `/proc/cpuinfo`, and see what appears under the “flags” label. Try this command:

`cat /proc/cpuinfo | grep flags`

If the list of flags includes the flag “sse” then your machine supports SSE instructions. If it also includes “sse2” then your machine supports SSE2 instructions. If your machine supports these instructions, it is better to use a version of ACML which was built to take advantage of them, for reasons of good performance.

The method of examining `/proc/cpuinfo` can also be used under Microsoft Windows if you have the Cygwin UNIX-like tools installed (see <http://www.cygwin.com/>) and run a bash shell. Note that AMD64 machines always support both SSE and SSE2 instructions, under both Linux and Windows. Older (32-bit) AMD chips may support SSE but not SSE2, or neither SSE nor SSE2 instructions. Other manufacturers' hardware may or may not support SSE or SSE2.

If you cannot determine whether or not your machine handles SSE or SSE2 instructions, you may prefer to assume that it does not. If you link to a version of ACML that was built

to use SSE or SSE2 instructions, and your machine does not in fact support them, it is likely that your program will halt due to encountering an “illegal instruction” - you may or may not be notified of this by the operating system.

Once you have answered the questions above, use these tables to decide which version of ACML to link against.

### Linux 64-bit

<i>Number of processors</i>	<i>Compilers</i>	<i>ACML install directory</i>
Single processor	GNU g77/gcc or compatible	acml3.1.0/gnu64
”	GNU gfortran/gcc	acml3.1.0/gfortran64
”	PGI pgf77/pgf90/pgcc	acml3.1.0/pgi64
”	PathScale pathf90/pathcc	acml3.1.0/pathscale64
Multi processor	PGI pgf77/pgf90/pgcc	acml3.1.0/pgi64_mp
”	PathScale pathf90/pathcc	acml3.1.0/pathscale64_mp

### Linux 32-bit

<i>Number of processors</i>	<i>Compilers</i>	<i>SSE supported</i>	<i>ACML install directory</i>
Single	GNU g77 / gcc or compat.	SSE and SSE2	acml3.1.0/gnu32
”	”	SSE, no SSE2	acml3.1.0/gnu32_nosse2
”	”	No SSE or SSE2	acml3.1.0/gnu32_nosse
”	GNU gfortran / gcc	SSE and SSE2	acml3.1.0/gfortran32
”	”	SSE, no SSE2	acml3.1.0/gfortran32_nosse2
”	”	No SSE or SSE2	acml3.1.0/gfortran32_nosse
”	PGI pgf77 / pgf90 / pgcc	SSE and SSE2	acml3.1.0/pgi32
”	”	SSE, no SSE2	acml3.1.0/pgi32_nosse2
”	”	No SSE or SSE2	acml3.1.0/pgi32_nosse
”	PathScale pathf90 / pathcc	SSE and SSE2	acml3.1.0/pathscale32
”	”	SSE, no SSE2	acml3.1.0/pathscale32_nosse2
”	”	No SSE or SSE2	acml3.1.0/pathscale32_nosse
Multiple	PGI pgf77 / pgf90 / pgcc	SSE and SSE2	acml3.1.0/pgi32_mp
”	PathScale pathf90 / pathcc	SSE and SSE2	acml3.1.0/pathscale32_mp

**Microsoft Windows 64-bit**

<i>Number of processors</i>	<i>Compilers</i>	<i>ACML install directory</i>
Single processor	PGI pgf77/pgf90/pgcc/MSVC	acml3.1.0/win64
Multi processor	PGI pgf77/pgf90/pgcc/MSVC	acml3.1.0/win64_mp

**Microsoft Windows 32-bit**

<i>Number of processors</i>	<i>Compilers</i>	<i>SSE supported</i>	<i>ACML install directory</i>
Single	GNU g77/gcc	SSE and SSE2	acml3.1.0/gnu32
"	"	SSE but no SSE2	acml3.1.0/gnu32_nosse2
"	"	No SSE or SSE2	acml3.1.0/gnu32_nosse
"	PGI pgf77/pgf90/pgcc	SSE and SSE2	acml3.1.0/pgi32
"	"	SSE but no SSE2	acml3.1.0/pgi32_nosse2
"	"	No SSE or SSE2	acml3.1.0/pgi32_nosse
"	Intel Fortran/Microsoft C	SSE and SSE2	acml3.1.0/ifort32
Multi	PGI pgf77/pgf90/pgcc	SSE and SSE2	acml3.1.0/pgi32_mp

**2.2 Accessing the Library (Linux)****2.2.1 Accessing the Library under Linux using GNU g77/gcc**

If the Linux 64-bit g77 version of ACML was installed in the default directory, /opt/acml3.1.0/gnu64, then the command:

```
g77 -m64 driver.f -L/opt/acml3.1.0/gnu64/lib -lacml
```

can be used to compile the program driver.f and link it to the ACML.

The ACML Library is supplied in both static and shareable versions, libacml.a and libacml.so, respectively. By default, the commands given above will link to the shareable version of the library, libacml.so, if that exists in the directory specified. Linking with the static library can be forced either by using the compiler flag `-static`, e.g.

```
g77 -m64 driver.f -L/opt/acml3.1.0/gnu64/lib -static -lacml
```

or by inserting the name of the static library explicitly in the command line, e.g.

```
g77 -m64 driver.f /opt/acml3.1.0/gnu64/lib/libacml.a
```

Notice that if the application program has been linked to the shareable ACML Library, then before running the program, the environment variable `LD_LIBRARY_PATH` must be set, for example, by the C-shell command:

```
setenv LD_LIBRARY_PATH /opt/acml3.1.0/gnu64/lib
```

where it is assumed that libacml.so was installed in the directory /opt/acml3.1.0/gnu64/lib (see the man page for `ld(1)` for more information about `LD_LIBRARY_PATH`).

The command

```
g77 -m32 driver.f -L/opt/acml3.1.0/gnu32/lib -lacml
```

will compile and link a 32-bit program with a 32-bit ACML.

To compile and link a 64-bit C program with a 64-bit ACML, invoke

```
gcc -m64 -I/opt/acml3.1.0/gnu64/include driver.c
-L/opt/acml3.1.0/gnu64/lib -lacml -lg2c
```

The switch "-I/opt/acml3.1.0/gnu64/include" tells the compiler to search the directory /opt/acml3.1.0/gnu64/include for the ACML C header file acml.h, which should be included by driver.c. Note that it is necessary to add the compiler run-time library -lg2c when linking the program.

### 2.2.2 Accessing the Library under Linux using GNU gfortran/gcc

If the Linux 64-bit gfortran version of ACML was installed in the default directory, /opt/acml3.1.0/gfortran64, then the command:

```
gfortran -m64 driver.f -L/opt/acml3.1.0/gfortran64/lib -lacml
```

can be used to compile the program driver.f and link it to the ACML.

The ACML Library is supplied in both static and shareable versions, libacml.a and libacml.so, respectively. By default, the commands given above will link to the shareable version of the library, libacml.so, if that exists in the directory specified. Linking with the static library can be forced either by using the compiler flag -static, e.g.

```
gfortran -m64 driver.f -L/opt/acml3.1.0/gfortran64/lib -static -lacml
```

or by inserting the name of the static library explicitly in the command line, e.g.

```
gfortran -m64 driver.f /opt/acml3.1.0/gfortran64/lib/libacml.a
```

Notice that if the application program has been linked to the shareable ACML Library, then before running the program, the environment variable LD\_LIBRARY\_PATH must be set. Assuming that libacml.so was installed in the directory /opt/acml3.1.0/gfortran64/lib, then LD\_LIBRARY\_PATH may be set by, for example, the C-shell command

```
setenv LD_LIBRARY_PATH /opt/acml3.1.0/gfortran64/lib
```

(See the man page for ld(1) for more information about LD\_LIBRARY\_PATH.)

The command

```
gfortran -m32 driver.f -L/opt/acml3.1.0/gfortran32/lib -lacml
```

will compile and link a 32-bit program with a 32-bit ACML.

To compile and link a 64-bit C program with a 64-bit ACML, invoke

```
gcc -m64 -I/opt/acml3.1.0/gfortran64/include driver.c
-L/opt/acml3.1.0/gfortran64/lib -lacml -lgfortran
```

The switch "-I/opt/acml3.1.0/gfortran64/include" tells the compiler to search the directory /opt/acml3.1.0/gfortran64/include for the ACML C header file acml.h, which should be included by driver.c. Note that it is necessary to add the gfortran compiler run-time library -lgfortran when linking the program.

### 2.2.3 Accessing the Library under Linux using PGI compilers pgf77/pgf90/pgcc

Similar commands apply for the PGI versions of ACML. For example,

```
pgf77 -tp=k8-64 -Mcache_align driver.f -L/opt/acml3.1.0/pgi64/lib -lacml
pgf77 -tp=k8-32 -Mcache_align driver.f -L/opt/acml3.1.0/pgi32/lib -lacml
```

will compile driver.f and link it to the ACML using 64-bit and 32-bit versions respectively. In the example above we are linking with the single-processor PGI version of ACML.

If you have an SMP machine and want to take best advantage of it, link against the PGI OpenMP version of ACML like this:

```
pgf77 -tp=k8-64 -mp -Mcache_align driver.f
      -L/opt/acml3.1.0/pgi64_mp/lib -lacml
pgf77 -tp=k8-32 -mp -Mcache_align driver.f
      -L/opt/acml3.1.0/pgi32_mp/lib -lacml
```

Note that the location of the ACML is now specified as pgi64\_mp or pgi32\_mp. The -mp flag is important - it tells pgf77 to link with the appropriate compiler OpenMP run-time library. Without it you might get an "unresolved symbol" message at link time. The -Mcache\_align flag is also important - it tells the compiler to align objects on cache-line boundaries.

The commands

```
pgcc -c -tp=k8-64 -mp -Mcache_align
      -I/opt/acml3.1.0/pgi64_mp/include driver.c
pgcc -tp=k8-64 -mp -Mcache_align driver.o
      -L/opt/acml3.1.0/pgi64_mp/lib -lacml -lpgftnrtl -lm
```

will compile driver.c and link it to the 64-bit ACML. Again, the -mp flag is important if you are linking to the PGI OpenMP version of ACML. The C compiler is instructed to search the directory /opt/acml3.1.0/pgi64\_mp/include for the ACML C header file acml.h, which should be included by driver.c, by using the switch "-I/opt/acml3.1.0/pgi64\_mp/include". Note that in the example we add the libraries -lpgftnrtl and -lm to the link command, so that required PGI compiler run-time libraries are found.

Note that in addition to the usual variants of ACML, the PGI 64-bit ACML also comes in "large\_arrays" variants. These variants were compiled with the PGI -Mlarge\_arrays switch to allow use of larger data arrays (see PGI compiler documentation for more information). Don't use these variants unless you really need to because the -Mlarge\_arrays switch may sometimes cause a slight performance penalty. To link to the "large arrays" variants of ACML for PGI compilers, use commands similar to those given above, but point to the large\_arrays ACML installations instead. For example:

```
pgf77 -tp=k8-64 -mp -Mcache_align driver.f
      -L/opt/acml3.1.0/pgi64_mp_large_arrays/lib -lacml
```

## 2.2.4 Accessing the Library under Linux using PathScale compilers pathf90/pathcc

Similar commands apply for the PathScale versions of ACML. For example,

```
pathf90 driver.f -L/opt/acml3.1.0/pathscale64/lib -lacml
```

will compile driver.f and link it to the ACML using the 64-bit version.

The commands

```
pathcc -c -I/opt/acml3.1.0/pathscale64/include driver.c
pathcc driver.o -L/opt/acml3.1.0/pathscale64/lib -lacml -lpathfortran
```

will compile driver.c and link it to the 64-bit ACML. The switch

```
-I/opt/acml3.1.0/pathscale64/include
```

tells the C compiler to search directory /opt/acml3.1.0/pathscale64/include for the ACML C header file acml.h, which should be included by driver.c. Note that in the example we

add the library `-lpathfortran` to the link command, so that the required PathScale compiler run-time library is found.

If you have an SMP machine and want to take best advantage of it, link against the PathScale OpenMP version of ACML like this:

```
pathf90 -mp driver.f -L/opt/acml3.1.0/pathscale64_mp/lib -lacml
pathf90 -mp driver.f -L/opt/acml3.1.0/pathscale32_mp/lib -lacml
```

Note that the location of the ACML is now specified as either `pathscale64_mp` or `pathscale32_mp`. The `-mp` flag is important - it tells `pathf90` to link with the appropriate compiler OpenMP run-time library. Without it you might get an "unresolved symbol" message at link time.

The commands

```
pathcc -c -mp -I/opt/acml3.1.0/pathscale64_mp/include driver.c
pathcc -mp driver.o -L/opt/acml3.1.0/pathscale64_mp/lib -lacml
-lpathfortran
```

will compile `driver.c` and link it to the 64-bit ACML. Again, the `-mp` flag is important if you are linking to the PathScale OpenMP version of ACML. The C compiler is instructed to search the directory `/opt/acml3.1.0/pathscale64_mp/include` for the ACML C header file `acml.h`, which should be included by `driver.c`, by using the switch `"-I/opt/acml3.1.0/pathscale64_mp/include"`. Note that in the example we add the library `-lpathfortran` to the link command, so that a required PathScale compiler run-time library is found.

The 32-bit ACML libraries come in several versions, applicable to hardware with or without SSE instructions (Streaming SIMD Extensions), and it is important to link to a library that is appropriate to your hardware. The variant library versions are distinguished by being in directories with different names.

### 2.2.5 Accessing the Library under Linux using compilers other than GNU, PGI or PathScale

It may be possible to link to the `g77/gcc` versions of ACML using other compilers, if they are compatible with `g77/gcc`. An important thing to note is that you will need to link in required compiler run time libraries. An example using the 32-bit Intel FORTRAN compiler *ifc* might look like this:

```
ifc driver.f -L/opt/acml3.1.0/gnu32/lib -lacml /usr/lib/libg2c.so
```

where `/usr/lib/libg2c.so` is required to resolve `g77` compiler run-time library symbols.

## 2.3 Accessing the Library (Microsoft Windows)

### 2.3.1 Accessing the Library under 32-bit Windows using GNU `g77/gcc`

Under Microsoft Windows®, for the `g77/gcc` version of ACML it is assumed that you have the Cygwin UNIX-like tools installed (see <http://www.cygwin.com/>), including the `g77/gcc` compiler and associated tools. Assuming you have installed the ACML in the default place, then in a DOS command prompt window, the command

`g77 driver.f "c:\Program Files\AMD\acml3.1.0\gnu32\lib\libacml.a"`  
 can be used to link the application program `driver.f` to the static library version of the ACML.

The `g77` version of the ACML Library is supplied in both static and shareable versions, `libacml.a` and `libacml.dll`, respectively. The command given above links to the static version of the library, `libacml.a`. To link to the DLL version, the command

```
g77 driver.f "c:\Program Files\AMD\acml3.1.0\gnu32\lib\libacml.dll"
```

can be used. Notice that if the application program has been linked to the DLL version of the ACML Library, then before running the program, the environment variable `PATH` must have been set to include the location of the DLL, for example by the DOS command:

```
PATH="c:\Program Files\AMD\acml3.1.0\gnu32\lib";%PATH%
```

where it was assumed that `libacml.dll` was installed in the directory `"c:\Program Files\AMD\acml3.1.0\gnu32\lib"`. Alternatively, the `PATH` environment variable may be set in the system category of the Windows control panel.

The command

```
gcc "-Ic:\Program Files\AMD\acml3.1.0\gnu32\include" driver.c
      "c:\Program Files\AMD\acml3.1.0\gnu32\lib\libacml.a" -lg2c
```

will compile `driver.c` and link it to the 32-bit `g77/gcc` version of ACML. The switch `"-Ic:\Program Files\AMD\acml3.1.0\gnu32\include"` tells the `gcc` compiler to search directory `"c:\Program Files\AMD\acml3.1.0\gnu32\include"` for the ACML C header file `acml.h`, which should be included by `driver.c`. Note that it is necessary to add the compiler run-time library `-lg2c` when linking the program.

### 2.3.2 Accessing the Library under 32-bit Windows using PGI compilers `pgf77/pgf90/pgcc`

To use the 32-bit Windows PGI version of ACML, use a command like

```
pgf77 -Mcache_align driver.f
      "c:\Program Files\AMD\acml3.1.0\pgi32\lib\libacml.a"
```

or

```
pgcc -c "-Ic:\Program Files\AMD\acml3.1.0\pgi32\include"
      -Mcache_align driver.c
pgcc -Mcache_align driver.o
      "c:\Program Files\AMD\acml3.1.0\pgi32\lib\libacml.a"
      -lpgftnrtl -lpgsse1 -lpgsse2 -lm
```

Note that in the example we link the program with `-lpgftnrtl -lpgsse1 -lpgsse2 -lm` so that required PGI run-time libraries are located.

If you have an SMP machine and want to take best advantage of it, link against the PGI OpenMP version of ACML like this:

```
pgf77 -mp -Mcache_align driver.f
      "c:\Program Files\AMD\acml3.1.0\pgi32\lib\libacml.a"
```

Note that the location of the ACML is now specified as `pgi32_mp`. The `-mp` flag is important - it tells `pgf77` to link with the appropriate compiler OpenMP run-time library. Without it you might get an "unresolved symbol" message at link time. The `-Mcache_align`



flag is also important - it tells the compiler to align objects on cache-line boundaries. The `-mp` flag is also required if you compile and link a C program to the `pgi32_mp` libraries.

### 2.3.3 Accessing the Library under 32-bit Windows using Microsoft C or Intel Fortran

To use the 32-bit Windows MSC/Intel Fortran version of ACML, use a command like

```
ifort /threads /libs:dll driver.f
      "c:\Program Files\AMD\acml3.1.0\ifort32\lib\libacml_dll.lib"
```

where `libacml_dll.lib` is the import library for the ACML DLL,

or

```
cl "-Ic:\Program Files\AMD\acml3.1.0\ifort32\include"
    /MD driver.c
    "c:\Program Files\AMD\acml3.1.0\ifort32\lib\libacml_dll.lib"
```

where `ifort` is the Intel Fortran command line compiler and `cl` is the Microsoft C command line compiler.

ACML can also be linked from inside a development environment such as Microsoft Visual Studio or Visual Studio.NET. Again, it is important to get compilation options correct. The directory `acml3.1.0\ifort32\examples\Projects` contains a few sample Visual Studio project directories showing how this can be done.

Note that in both examples above we linked to a DLL version of ACML, and so before running the resulting programs the environment variable `PATH` must be set to include the location of the DLL. Assuming that `libacml_dll.dll` was installed in `"c:\Program Files\AMD\acml3.1.0\ifort32\lib"`, `PATH` may be set by, for example, the DOS command

```
PATH="c:\Program Files\AMD\acml3.1.0\ifort32\lib";%PATH%
```

Alternatively, the `PATH` environment variable may be set in the system category of the Windows control panel.

ACML also comes as a static (non-DLL) library, named `libacml.lib`, in the same directory as the DLL. If you link to the static library instead of the DLL import library then there is no need to set the `PATH`.

### 2.3.4 Accessing the Library under 32-bit Windows using the Compaq Visual Fortran compiler

The win32 Intel Fortran variant of ACML can be used with the Compaq Visual Fortran compiler as follows:

```
f90 /iface:cref,nomixed_str_len_arg /threads /libs:dll driver.f
      "c:\Program Files\AMD\acml3.1.0\ifort32\lib\libacml_dll.lib"
```

where `f90` is the Compaq Visual Fortran command line compiler and `libacml_dll.lib` is the import library for the ACML DLL. The switch `/iface:cref,nomixed_str_len_arg` used on the `f90` compiler command line is important - it tells the compiler to use a calling convention equivalent to the default Intel Fortran calling convention, rather than the default `cvf_stdcall` calling convention. If you forget to use this switch your program is likely to crash on execution.

### 2.3.5 Accessing the Library under 32-bit Windows using the Salford Ftn95 compiler

The win32 Intel Fortran variant of ACML can be used with the Salford ftn95 compiler as follows:

```
ftn95 driver.f
```

The resulting object file can be linked using the Salford linker, slink, for example like this:

```
slink driver.obj install_dir\libacml_dll.dll
```

where install\_dir is the location of the DLL. The full pathname of install\_dir should be specified to the DLL and should be enclosed within quotes if it contains spaces. It is worth emphasising that the linker should link directly against the DLL itself, not the libacml\_dll.lib import library.

### 2.3.6 Accessing the Library under 64-bit Windows

Under 64-bit versions of Windows, ACML 3.1.0 comes as a static (.LIB) library or a DLL. The libraries can be used with the PGI compilers pgf77/pgf90/pgcc or with the Microsoft C compiler.

To link with the 64-bit Windows DLL library version of ACML, in a DOS command prompt use a command like

```
pgf77 driver.f c:/acml3.1.0/win64/lib/libacml_dll.lib
```

where libacml\_dll.lib is the import library for the DLL. In the example above we are linking with the single-processor WIN64 version of ACML.

If you have an SMP machine and want to take best advantage of it, link against the WIN64 OpenMP version of ACML like this:

```
pgf77 driver.f c:/acml3.1.0/win64_mp/lib/libacml_dll.lib
```

For the OpenMP version of ACML, if you link to the static library libacml.lib rather than the DLL import library libacml\_dll.lib, you will also need to use the PGI compiler flag -mp in order to tell the compiler to link with the appropriate compiler OpenMP run-time library. Without it you might get an "unresolved symbol" message at link time. This should not be necessary when linking to the ACML DLL because the DLL itself knows that it depends on the run-time library; but using the -mp flag in any case will do no harm.

Note that the performance of OpenMP code produced with the PGI WIN64 compilers depends on environment variables named *MP\_BIND* and *MP\_SPIN*, which control how multiple threads behave (see PGI compiler documentation for discussion of these variables). For ACML, empirical experiments show that higher values of *MP\_SPIN* than the default are likely to give better performance. We recommend that users set *MP\_BIND*=yes and *MP\_SPIN*=100000000.

Under WIN64, to compile and link a C program, the commands

```
pgcc driver.c -Ic:/acml3.1.0/win64/include
c:/acml3.1.0/win64/lib/libacml_dll.lib
pgcc -mp driver.c -Ic:/acml3.1.0/win64/include
c:/acml3.1.0/win64_mp/lib/libacml_dll.lib
```

will link against the single-threaded DLL and multi-threaded versions of ACML respectively.

To use the Microsoft C command line compiler, *cl*, use commands like this:

```

cl driver.c -Ic:/acml3.1.0/win64/include
               c:/acml3.1.0/win64/lib/libacml_dll.lib
cl driver.c -Ic:/acml3.1.0/win64/include
               c:/acml3.1.0/win64_mp/lib/libacml_dll.lib

```

for single- and multi-threaded ACML variants respectively.

Note that in addition to the usual variants of ACML, the Windows 64-bit ACML also comes in “large\_arrays” variants. These variants were compiled with the PGI -Mlarge\_arrays switch to allow use of larger data arrays (see PGI compiler documentation for more information). Don’t use these variants unless you really need to because the -Mlarge\_arrays switch may sometimes cause a slight performance penalty. To link to the “large arrays” variants of ACML for PGI compilers, use commands similar to those given above, but point to the large\_arrays ACML installations instead. For example:

```
pgf77 driver.f c:/acml3.1.0/win64_large_arrays/lib/libacml_dll.lib
```

## 2.4 Accessing the Library (Solaris)

### 2.4.1 Accessing the Library under Solaris

If the Solaris 64-bit f95 version of ACML was installed in the default directory, /opt/acml3.1.0/sun64, then the command:

```
f95 -xarch=amd64 driver.f -L/opt/acml3.1.0/sun64/lib -lacml
```

can be used to compile the program driver.f and link it to the ACML.

The ACML Library is supplied in both static and shareable versions, libacml.a and libacml.so, respectively. By default, the commands given above will link to the shareable version of the library, libacml.so, if that exists in the directory specified. Linking with the static library can be forced either by using the compiler flag -Bstatic, e.g.

```
f95 -xarch=amd64 driver.f -L/opt/acml3.1.0/sun64/lib -Bstatic -lacml
```

or by inserting the name of the static library explicitly in the command line, e.g.

```
f95 -xarch=amd64 driver.f /opt/acml3.1.0/sun64/lib/libacml.a
```

Notice that if the application program has been linked to the shareable ACML Library, then before running the program, the environment variable LD\_LIBRARY\_PATH must be set, for example, by the C-shell command:

```
setenv LD_LIBRARY_PATH /opt/acml3.1.0/sun64/lib
```

where it is assumed that libacml.so was installed in the directory /opt/acml3.1.0/sun64/lib (see the man page for ld(1) for more information about LD\_LIBRARY\_PATH.).

The command

```
f95 -xarch=sse2 driver.f -L/opt/acml3.1.0/sun32/lib -lacml
```

will compile and link a 32-bit program with a 32-bit ACML.

To compile and link a 64-bit C program with a 64-bit ACML, invoke

```
cc -xarch=amd64 -I/opt/acml3.1.0/sun64/include driver.c
    -L/opt/acml3.1.0/sun64/lib -lacml -lfsu -lsunmath -lm
```

The switch "-I/opt/acml3.1.0/sun64/include" tells the compiler to search the directory /opt/acml3.1.0/sun64/include for the ACML C header file acml.h, which should be included

by `driver.c`. Note that it is necessary to add the Sun compiler run-time libraries `-lfsw -lsunmath -lm` when linking the program.

## 2.5 ACML FORTRAN and C interfaces

All routines in ACML come with both FORTRAN and C interfaces. The FORTRAN interfaces typically follow the relevant standard (e.g. LAPACK, BLAS). Here we document how a C programmer should call ACML routines.

In C code that uses ACML routines, be sure to include the header file `<acml.h>`, which contains function prototypes for all ACML C interfaces. The header file also contains C prototypes for FORTRAN interfaces, thus the C programmer could call the FORTRAN interfaces from C, though there is little reason to do so.

C interfaces to ACML routines differ from FORTRAN interfaces in the following major respects:

- The FORTRAN interface names are appended by an underscore (except for the Windows 32-bit Microsoft C/Intel Fortran version of ACML, where FORTRAN interface names are distinguished from C by being upper case rather than lower case - this is the default for the Intel Fortran compiler)
- The C interfaces contain no workspace arguments; all workspace memory is allocated internally.
- Scalar input arguments are passed by value in C interfaces. FORTRAN interfaces pass all arguments (except for character string *length* arguments that are normally hidden from FORTRAN programmers) by reference.
- Most arguments that are passed as character string pointers to FORTRAN interfaces are passed by value as single characters to C interfaces. The character string *length* arguments of FORTRAN interfaces are not required in the C interfaces.
- Unlike FORTRAN, C has no native *complex* data type. ACML C routines which operate on complex data use the types *complex* and *doublecomplex* defined in `<acml.h>` for single and double precision computations respectively. Some of the programs in the ACML examples directory (see [Section 2.8 \[Examples\]](#), [page 15](#)) make use of these types.

It is important to note that in both the FORTRAN and C interfaces, 2-dimensional arrays are assumed to be stored in column-major order. e.g. the matrix

$$A = \begin{pmatrix} 1.0 & 2.0 \\ 3.0 & 4.0 \end{pmatrix}$$

would be stored in memory as 1.0, 3.0, 2.0, 4.0. This storage order corresponds to a FORTRAN-style 2-D array declaration `A(2,2)`, but not to an array declared as `a[2][2]` in C which would be stored in row-major order as 1.0, 2.0, 3.0, 4.0.

As an example, compare the FORTRAN and C interfaces of LAPACK routine `dsytrf` as implemented in ACML.

FORTRAN:

```
void dsytrf_(char *uplo, int *n, double *a, int *lda, int *ipiv,
            double *work, int *lwork, int *info, int uplo_len);
```

C:

```
void dsytrf(char uplo, int n, double *a, int lda, int *ipiv,
           int *info);
```

C code calling both the above variants might look like this:

```
double *a;
int *ipiv;
double *work;
int n, lda, lwork, info;

/* Assume that all arrays and variables are allocated and
   initialized as required by dsytrf. */

/* Call the FORTRAN version of dsytrf. The first argument
   is a character string, and the last argument is the
   length of that string. The input scalar arguments n, lda
   and lwork, as well as the output scalar argument info,
   are all passed by reference. */
dsytrf_("Upper", &n, a, &lda, ipiv, work, &lwork, &info, 5);

/* Call the C version of dsytrf. The first argument is a
   character, workspace is not required, and input scalar
   arguments n and lda are passed by value. Output scalar
   argument info is passed by reference. */
dsytrf('U', n, a, lda, ipiv, &info);
```

## 2.6 Library Version and Build Information

This document is applicable to version 3.1.0 of ACML. The utility routine `acmlversion` can be called to obtain the major, minor and patch version numbers of the installed ACML. This routine returns three integers; the major, minor and patch version numbers, respectively.

The utility routine `acmlinfo` can be called to obtain information on the compiler used to build ACML, the version of the compiler, and the options used for building the Library. This subroutine takes no arguments and prints the information to the current standard output.

FORTRAN specifications:

`ACMLVERSION (MAJOR, MINOR, PATCH)` [SUBROUTINE]

*MAJOR, MINOR, PATCH* [INTEGER]

`ACMLINFO ()` [SUBROUTINE]

C specifications:

`void acmlversion (int *major, int *minor, int *patch);` [function]

`void acmlinfo (void);` [function]

## 2.7 Library Documentation

The /Doc subdirectory of the top ACML installation directory, (e.g. /opt/acml3.1.0/Doc under Linux, or c:\Program Files\AMD\acml3.1.0\Doc under Windows), should contain this document in the following formats:

- Printed Manual / PDF format – acml.pdf
- Info Pages – acml.info (Linux only)
- Html – html/index.html
- Plain text – acml.txt

Under Linux the info file can be read using *info* after updating the environment variable INFOPATH to include the doc subdirectory of the ACML installation directory, e.g.

```
% setenv INFOPATH ${INFOPATH}:/opt/acml3.1.0/Doc
```

```
% info acml
```

or simply by using the full name of the file:

```
% info /opt/acml3.1.0/Doc/acml.info
```

## 2.8 Example programs calling ACML

The /examples subdirectory of the top ACML installation directory (for example, possible default locations are /opt/acml3.1.0/gnu64/examples under Linux, or, under windows, c:\Program Files\AMD\acml3.1.0\gnu32\examples), contains example programs showing how to call the ACML, along with a GNUmakefile to build and run them. Examples of calling both FORTRAN and C interfaces are included. They may be used as an ACML installation test.

Depending on where your copy of the ACML is installed, and which compiler and flags you wish to use, it may be necessary to modify some variables in the GNUmakefile before using it.

The 32-bit Windows versions of ACML assume that you have the Cygwin UNIX-like tools installed, and can use the *make* command that comes with them to build the examples.

For the 64-bit Windows version of ACML, it is not necessary to have the Cygwin tools. The examples directory contains a bat script, *acmlexample.bat*, which can be used to run one of the example programs. Another bat script, *acmlallexamples.bat*, builds and runs all the examples in the directory. Alternatively, if you do have the Cygwin tools installed, you can use the GNUmakefile to build the examples.

If you need more example programs showing how to call LAPACK routines from Fortran, we refer you to this web page:

<http://www.nag.com/lapack/>

Here you will find examples for all double precision LAPACK driver routines, and all of these should work when linked with ACML. Note that as well as the example programs themselves, it is necessary to download and compile a small amount of utility code used by the programs. See the web page for detailed instructions.

### 3 BLAS: Basic Linear Algebra Subprograms

The BLAS are a set of well defined basic linear algebra operations ([1], [2], [3]). These operations are subdivided into three groups:

- Level 1: operations acting on vectors only (e.g. dot product)
- Level 2: matrix-vector operations (e.g. matrix-vector multiplication)
- Level 3: matrix-matrix operations (e.g. matrix-matrix multiplication)

Efficient machine-specific implementations of the BLAS are available for many modern high-performance computers. The implementation of higher level linear algebra algorithms on these systems depends critically on the use of the BLAS as building blocks. AMD provides, as part of the ACML, an implementation of the BLAS optimized for performance on AMD64 processors.

For any information relating to the BLAS please refer to the BLAS FAQ:

<http://www.netlib.org/blas/faq.html>

ACML also includes interfaces to the extensions to Level 1 BLAS known as the sparse BLAS. These routines perform operations on a sparse vector  $x$  which is stored in compressed form and a vector  $y$  in full storage form. See reference [4] for more information.

## 4 LAPACK: Package of Linear Algebra Subroutines

### 4.1 Introduction to LAPACK

LAPACK ([5]) is a library of FORTRAN 77 subroutines for solving commonly occurring problems in numerical linear algebra. LAPACK components can solve systems of linear equations, linear least squares problems, eigenvalue problems and singular value problems. Dense and banded matrices are provided for, but not general sparse matrices. In all areas, similar functionality is provided for real and complex matrices.

LAPACK routines are written so that as much as possible of the computations is performed by calls to the BLAS. The efficiency of LAPACK routines depends, in large part, on the efficiency of the BLAS being called. Block algorithms are employed wherever possible to maximize the use of calls to level 3 BLAS, which generally run faster than lower level BLAS due to the high number of operations per memory access.

The performance of some of the LAPACK routines has been further improved by reworking the computational algorithms. Some of the LAPACK routines contained in ACML are therefore based on code that is different from the LAPACK sources available in the public domain. In all these cases the algorithmic and numerical properties of the original LAPACK routines have been strictly preserved. Furthermore, key LAPACK routines have been treated using OpenMP to take advantage of multiple processors when running on SMP machines. Your application will automatically benefit when you link with the OpenMP versions of ACML.

### 4.2 Reference sources for LAPACK

The LAPACK homepage can be accessed on the World Wide Web via the URL address:

<http://www.netlib.org/lapack/>

The on-line version of the Lapack User's Guide, Third Edition ([5]) is available from this homepage, or directly using the URL:

<http://www.netlib.org/lapack/lug/index.html>

The standard source code is available for download from netlib, with separate distributions for UNIX/Linux and Windows® installations:

<http://www.netlib.org/lapack/lapack.tgz>  
<http://www.netlib.org/lapack/lapack-pc.zip>

A list of known problems, bugs, and compiler errors for LAPACK, as well as an errata list for the LAPACK User's Guide ([5]), is maintained on netlib

[http://www.netlib.org/lapack/release\\_notes](http://www.netlib.org/lapack/release_notes)

A LAPACK FAQ (Frequently Asked Questions) file can also be accessed via the LAPACK homepage

<http://www.netlib.org/lapack/faq.html>



### 4.3 LAPACK block sizes, ILAENV and ILAENVSET

As described in Section 6.2 of the LAPACK User's Guide, block sizes and other parameters used by various LAPACK routines are returned by the LAPACK inquiry function ILAENV. In ACML, values returned by ILAENV have been chosen to achieve very good performance on a wide variety of hardware and problem sizes.

In general it is unlikely that you will want or need to be concerned with these parameters. However, in some cases it may be that a default value returned by ILAENV is not optimal for your particular hardware and problem size. Following the advice in the LAPACK User's Guide may enable you to choose a better value in some circumstances.

For convenience, ACML includes a subroutine which allows you to override default values returned by ILAENV if you have superior knowledge. The routine is named ILAENVSET and has the following specification.

```
ILAENVSET (ISPEC,NAME,OPTS,N1,N2,N3,N4,NVALUE,INFO)           [SUBROUTINE]
```

INTEGER ISPEC [Input]  
 On input: *ISPEC* specifies the parameter to be set (see Section 6.2 of the LAPACK User's Guide for details).

CHARACTER\*(\*) NAME [Input]  
 On input: *NAME* specifies the name of the LAPACK subroutine for which the parameter is to be set.

CHARACTER\*(\*) OPTS [Input]  
 On input: *OPTS* is a character string of options to the subroutine.

INTEGER N1, N2, N3, N4 [Input]  
 On input: *N1*, *N2*, *N3* and *N4* are problem dimensions. A value of -1 means that the dimension is unused or irrelevant.

INTEGER NVALUE [Input]  
 On input: *NVALUE* is the value to be set for the parameter specified by *ISPEC*. This value will be retrieved by any future call of ILAENV with similar arguments, including the call of ILAENV coming directly from the routine specified by argument *NAME*. In most cases, but not all, the value set will apply irrespective of the values of arguments *OPTS*, *N1*, *N2*, *N3* and *N4*.

INTEGER INFO [Output]  
 On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

All arguments of ILAENVSET apart from the last two, *NVALUE* and *INFO*, are identical to the arguments of ILAENV. ILAENVSET should be called *before* you call the LAPACK routine in question.

It should be noted that not all LAPACK routines make use of the ILAENV mechanism (because not all routines use blocked algorithms or require other tuning parameters). Calls of ILAENVSET with argument *NAME* set to the name of such a routine will fail with *INFO*=0. In addition, the ACML versions of some important routines that do use blocked algorithms, such as the QR factorization routine DGEQRF, bypass ILAENV because they make use of a

different tuning system which is independent of standard LAPACK. For all such routines, ILAENVSET can still be called with no error exit, but calls will have no effect on performance of the routine.

Below we give examples of how to call ILAENVSET in both FORTRAN and C.

Example (FORTRAN code):

```

      INTEGER ILO, IHI, INFO, N, NS
      CHARACTER COMPZ, JOB
      INTEGER ILAENV
      EXTERNAL ILAENV, ILAENVSET
      JOB = 'E'
      COMPZ = 'I'
      N = 512
      ILO = 1
      IHI = 512
C    Check the default shift parameter (ISPEC=4) used by DHSEQR
      NS = ILAENV(4, 'DHSEQR', JOB//COMPZ, N, ILO, IHI, -1)
      WRITE (*,*) 'Default NS = ', NS
C    Set a new value 5 for the shift parameter
      CALL ILAENVSET(4, 'DHSEQR', JOB//COMPZ, N, ILO, IHI, -1, 5, INFO)
C    Then check the shift parameter again
      NS = ILAENV(4, 'DHSEQR', JOB//COMPZ, N, ILO, IHI, -1)
      WRITE (*,*) 'Revised NS = ', NS
      END

```

Example (C code):

```
#include <acml.h>
#include <stdio.h>
int main(void)
{
    int n=512, ilo=1, ihi=512, ns, info;
    char compz = 'I', job = 'E', opts[3];
    opts[0] = job;
    opts[1] = compz;
    opts[2] = '\0';
    /* Check the default shift parameter (ISPEC=4) used by DHSEQR */
    ns = ilaenv(4, "DHSEQR", opts, n, ilo, ihi, -1);
    printf("Default ns = %d\n", ns);
    /* Set a new value 5 for the shift parameter */
    ilaenvset(4, "DHSEQR", opts, n, ilo, ihi, -1, 5, &info);
    /* Then check the shift parameter again */
    ns = ilaenv(4, "DHSEQR", opts, n, ilo, ihi, -1);
    printf("Revised ns = %d\n", ns);
    return 0;
}
```

## 5 Fast Fourier Transforms (FFTs)

### 5.1 Introduction to FFTs

There are two main types of Discrete Fourier Transform (DFT):

- routines for the transformation of complex data: in the ACML, these routines have names beginning with **ZFFT** or **CFFT**, for double and single precision, respectively;
- routines for the transformation of real to complex data and vice versa: in the ACML the names for the former begin with **DZFFT** or **SCFFT**, for double and single precision, respectively; the names for the latter begin with **ZDFFT** or **CSFFT**.

The following subsections provide definitions of the DFT for complex and real data types, and some guidelines on the efficient use of the ACML FFT routines.

#### 5.1.1 Transform definitions and Storage for Complex Data

The simplest transforms to describe are those performed on sequences of complex data. Such data are stored as arrays of type complex. The result of a complex FFT is also a complex sequence of the same length and, for the simple interfaces, is written back to the original array. Where multiple ( $m$ , say), same-length sequences (of length  $n$ ) of complex data are to be transformed, the sequences are held in a single complex array; in the simple interfaces the array will be of length  $m * n$  containing  $m$  end-to-end sequences and the results of the  $m$  FFTs are returned in the original array. Expert interfaces are provided which give: greater flexibility in the storage of the original data and results, user provided scaling, and whether results should be written to a separate array or not.

The definition of a complex DFT used here is given by:

$$\tilde{x}_j = \frac{1}{\sqrt{n}} \sum_{k=0}^{n-1} x_k \exp\left(\pm i \frac{2\pi jk}{n}\right) \text{ for } j = 0, 1, \dots, n-1$$

where  $x_k$  are the complex data to be transformed,  $\tilde{x}_j$  are the transformed data, and the sign of  $\pm$  determines the direction of the transform:  $(-)$  for forward and  $(+)$  for backward. Note that, in this definition, both directional transforms have the same scaling and performing both consecutively recovers the original data; this is the prescribed scaling provided in the simple FFT interfaces, whereas, in the expert interfaces, the scaling factor must be supplied by the user.

For the simple interfaces, a two dimensional array of complex data, with  $m$  rows and  $n$  columns is stored in the same order as a set of  $n$  sequences of length  $m$  (as described above). That is, column elements are stored contiguously and the first element of the next column follows the last element of the current column. In the expert interfaces, column elements may be separated by a fixed step length (increment) while row elements may be separated by a second increment; if the first increment is 1 and the second increment is  $m$  then we have the same storage as in the simple interface.

The definition of a complex 2D DFT used here is given by:

$$\tilde{x}_{jp} = \frac{1}{\sqrt{m * n}} \sum_{l=0}^{m-1} \sum_{k=0}^{n-1} x_{kl} \exp\left(\pm i \frac{2\pi jk}{n}\right) \exp\left(\pm i \frac{2\pi pl}{m}\right)$$

for  $j = 0, 1, \dots, n-1$  and  $l = 0, 1, \dots, m-1$ , where  $x_{kl}$  are the complex data to be transformed,  $\tilde{x}_{jp}$  are the transformed data, and the sign of  $\pm$  determines the direction of the transform.

### 5.1.2 Transform definitions and Storage for Real Data

The DFT of a sequence of real data results in a special form of complex sequence known as a Hermitian sequence. The symmetries defining such a sequence mean that it can be fully represented by a set of  $n$  real values, where  $n$  is the length of the original real sequence. It is therefore conventional for the array containing the real sequence to be overwritten by such a representation of the transformed Hermitian sequence.

If the original sequence is purely real valued, i.e.  $z_j = x_j$ , then the definition of the real DFT used here is given by:

$$\tilde{z}_j = a_j + ib_j = \frac{1}{\sqrt{n}} \sum_{k=0}^{n-1} x_k \exp\left(-i \frac{2\pi jk}{n}\right) \text{ for } j = 0, 1, \dots, n-1$$

where  $x_k$  are the real data to be transformed,  $\tilde{z}_j$  are the transformed complex data.

In full complex representation, the Hermitian sequence would be a sequence of  $n$  complex values  $Z(i)$  for  $i = 0, 1, \dots, n-1$ , where  $Z(n-j)$  is the complex conjugate of  $Z(j)$  for  $j = 1, 2, \dots, (n-1)/2$ ;  $Z(0)$  is real valued; and, if  $n$  is even,  $Z(n/2)$  is real valued. In ACML, the representation of Hermitian sequences used on output from DZFFT routines and on input to ZDFFT routines is as follows:

let  $X$  be an array of length  $N$  and with first index 0,

- $X(i)$  contains the real part of  $Z(i)$  for  $i = 0, \dots, N/2$
- $X(N-i)$  contains the imaginary part of  $Z(i)$  for  $i = 1, \dots, (N-1)/2$

Also, given a Hermitian sequence, the discrete transform can be written as:

$$x_j = \frac{1}{\sqrt{n}} \left( a_0 + 2 \sum_{k=1}^{n/2-1} \left( a_k \cos\left(\frac{2\pi jk}{n}\right) - b_k \sin\left(\frac{2\pi jk}{n}\right) \right) + a_{n/2} \right)$$

where  $a_{n/2} = 0$  if  $n$  is odd, and  $\tilde{z}_k = a_k + ib_k$  is the Hermitian sequence to be transformed. Note that, in the above definitions, both transforms have the same (negative) sign in the exponent; performing both consecutively does not recover the original data. To recover original real data, or otherwise to perform an inverse transform on a set of Hermitian data, the Hermitian data must be conjugated prior to performing the transform (i.e. changing the sign of the stored imaginary parts).

### 5.1.3 Efficiency

The efficiency of the FFT is maximized by choosing the sequence length to be a power of 2. Good efficiency can also be achieved when the sequence length has small prime factors, up to a factor 13; however, the time taken for an FFT increases as the size of the prime factor increases.

### 5.1.4 Default and Generated Plans

For those FFT routines that can be initialized prior to computing the FFTs, the initialization can be performed in one of two ways. In either case, initialization involves the storing of the factorization of  $N$ , and the twiddle factors associated with this factorization, in the communication array *COMM*.

The simpler way to initialize is by setting the argument *MODE* to zero. This means that a default plan, for the given input dimensions, is used to calculate the FFT. This has the advantage that the initialization phase is very quick and is generally a small fraction of the time required to perform the FFT computation. However, for some problem dimensions the default plan may not be optimal, especially where there is a mixture of prime factors.

Under some circumstances, optimality of performance of an FFT computation may be crucial. For example, where a very large number of FFTs are to be performed on problems of a fixed size (e.g.  $N$  remains the same), then it is best to initialize by setting the argument *MODE* to 100. This will time a number of plans (this number can be quite large when  $N$  has a significant number of prime factors) and initialize using the plan with the best time. Using this form of initialization can, potentially, lead to significant improvements in the performance of the FFT computation for the given dimensions.

Where problem dimensions will not change over a number of runs of a program, the communication array could, for example, be written out to a file during an initialisation run, and then read in from the same file on subsequent computation runs. This would be effective for problem dimensions that have a large number of possible plans (factor orderings and groupings) and therefore take a significant amount of time to find the optimal plan.

Please consult the individual FFT routine documents to determine whether plan generation is enabled.

## 5.2 FFTs on Complex Sequences

### 5.2.1 FFT of a single sequence

The routines documented here compute the discrete Fourier transform (DFT) of a sequence of complex numbers in either single or double precision arithmetic. The DFT is computed using a highly-efficient FFT algorithm. There are two sets of interfaces available: simple drivers and expert drivers. The simple drivers perform in-place transforms on data held contiguously in memory using a fixed scaling factor; these are simpler to use and are sufficient for many problems. The expert drivers offer greater flexibility by including a number of additional arguments. These allow you to control: the scaling factor applied; whether the result should be output to a separate vector; and, the increments used in storing successive elements of both the input sequence and the result.

## ZFFT1D Routine Documentation

ZFFT1D (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by ZFFT1D.

On input:

- *MODE*=0 : only default initializations (specific to *N*) are performed; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1D.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1D.
- *MODE*=-2 : initializations and a forward transform are performed.
- *MODE*=2 : initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations are performed, but first a plan is generated. This plan is chosen based on the fastest FFT computation for a subset of all possible plans.

INTEGER *N* [Input]

On input: *N* is the length of the complex sequence *X*

COMPLEX\*16 *X(N)* [Input/Output]

On input: *X* contains the complex sequence of length *N* to be transformed.

On output: *X* contains the transformed sequence.

COMPLEX\*16 *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

CALL ZFFT1D(0,N,X,COMM,INFO)
CALL ZFFT1D(-1,N,X,COMM,INFO)
CALL ZFFT1D(-1,N,Y,COMM,INFO)
DO 10 I = 1, N
    X(I) = X(I)*DCONJG(Y(I))
10 CONTINUE
CALL ZFFT1D(1,N,X,COMM,INFO)
```



## CFFT1D Routine Documentation

CFFT1D (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by CFFT1D.

On input:

- *MODE*=0 : only default initializations (specific to *N*) are performed; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1D.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1D.
- *MODE*=-2 : (default) initializations and a forward transform are performed.
- *MODE*=2 : (default) initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations are performed, but first a plan is generated. This plan is chosen based on the fastest FFT computation for a subset of all possible plans.

INTEGER *N* [Input]

On input: *N* is the length of the complex sequence *X*

COMPLEX *X(N)* [Input/Output]

On input: *X* contains the complex sequence of length *N* to be transformed.

On output: *X* contains the transformed sequence.

COMPLEX *COMM(5\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

CALL CFFT1D(0,N,X,COMM,INFO)
CALL CFFT1D(-1,N,X,COMM,INFO)
CALL CFFT1D(-1,N,Y,COMM,INFO)
DO 10 I = 1, N
    X(I) = X(I)*CONJG(Y(I))
10 CONTINUE
CALL CFFT1D(1,N,X,COMM,INFO)
```

## ZFFT1DX Routine Documentation

ZFFT1DX (*MODE,SCALE,INPL,N,X,INCX,Y,INCY,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by ZFFT1DX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1DX.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1DX.
- *MODE*=-2 : (default) initializations and a forward transform are performed.
- *MODE*=2 : (default) initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

DOUBLE PRECISION *SCALE* [Input]

On input: *SCALE* is the scaling factor to apply to the output sequence

LOGICAL *INPL* [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequence; otherwise the output sequence is returned in *Y*.

INTEGER *N* [Input]

On input: *N* is the number of elements to be transformed

COMPLEX\*16 *X*(1+(*N*-1)\**INCX*) [Input/Output]

On input: *X* contains the complex sequence of length *N* to be transformed, with the *i*th element stored in *X*(1+(*i*-1)\**INCX*).

On output: if *INPL* is .TRUE. then *X* contains the transformed sequence in the same locations as on input; otherwise *X* remains unchanged.

INTEGER *INCX* [Input]

On input: *INCX* is the increment used to store successive elements of a sequence in *X*.

Constraint: *INCX* > 0.

COMPLEX\*16 *Y*(1+(*N*-1)\**INCY*) [Output]

On output: if *INPL* is .FALSE. then *Y* contains the transformed sequence, with the *i*th element stored in *Y*(1+(*i*-1)\**INCY*); otherwise *Y* is not referenced.

INTEGER INCY [Input]

On input: *INCY* is the increment used to store successive elements of a sequence in *Y*. If *INPL* is *.TRUE.* then *INCY* is not referenced.

Constraint: *INCY* > 0.

COMPLEX\*16 COMM(5\*N+100) [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
C      Forward FFTs are performed unscaled and in-place on contiguous
C      vectors X and Y following initialization. Manipulations on
C      resultant Fourier coefficients are stored in X which is then
C      transformed back.
C
      SCALE = 1.0D0
      INPL = .TRUE.
      CALL ZFFT1DX(0,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)
      CALL ZFFT1DX(-1,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)
      CALL ZFFT1DX(-1,SCALE,INPL,N,Y,1,DUM,1,COMM,INFO)
      DO 10 I = 1, N
          X(I) = X(I)*DCONJG(Y(I))/DBLE(N)
10  CONTINUE
      CALL ZFFT1DX(1,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)
```

**CFFT1DX Routine Documentation**

CFFT1DX (*MODE,SCALE,INPL,N,X,INCX,Y,INCY,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by CFFT1DX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1DX.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1DX.
- *MODE*=-2 : (default) initializations and a forward transform are performed.
- *MODE*=2 : (default) initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

REAL *SCALE* [Input]

On input: *SCALE* is the scaling factor to apply to the output sequence

LOGICAL *INPL* [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequence; otherwise the output sequence is returned in *Y*.

INTEGER *N* [Input]

On input: *N* is the number of elements to be transformed

COMPLEX *X*(1+(*N*-1)\**INCX*) [Input/Output]

On input: *X* contains the complex sequence of length *N* to be transformed, with the *i*th element stored in *X*(1+(*i*-1)\**INCX*).

On output: if *INPL* is .TRUE. then *X* contains the transformed sequence in the same locations as on input; otherwise *X* remains unchanged.

INTEGER *INCX* [Input]

On input: *INCX* is the increment used to store successive elements of a sequence in *X*.

Constraint: *INCX* > 0.

COMPLEX *Y*(1+(*N*-1)\**INCY*) [Output]

On output: if *INPL* is .FALSE. then *Y* contains the transformed sequence, with the *i*th element stored in *Y*(1+(*i*-1)\**INCY*); otherwise *Y* is not referenced.

INTEGER INCY [Input]

On input: *INCY* is the increment used to store successive elements of a sequence in *Y*. If *INPL* is *.TRUE.* then *INCY* is not referenced.

Constraint: *INCY* > 0.

COMPLEX COMM(5\*N+100) [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

C      Forward FFTs are performed unscaled and in-place on contiguous
C      vectors X and Y following initialization. Manipulations on
C      resultant Fourier coefficients are stored in X which is then
C      transformed back.
C
      SCALE = 1.0
      INPL = .TRUE.
      CALL CFFT1DX(0,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)
      CALL CFFT1DX(-1,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)
      CALL CFFT1DX(-1,SCALE,INPL,N,Y,1,DUM,1,COMM,INFO)
      DO 10 I = 1, N
          X(I) = X(I)*CONJG(Y(I))/REAL(N)
10    CONTINUE
      CALL CFFT1DX(1,SCALE,INPL,N,X,1,DUM,1,COMM,INFO)

```

### 5.2.2 FFT of multiple complex sequences

The routines documented here compute the discrete Fourier transforms (DFTs) of a number of sequences of complex numbers in either single or double precision arithmetic. The sequences must all have the same length. The DFTs are computed using a highly-efficient FFT algorithm. There are two sets of interfaces available: simple drivers and expert drivers. The simple drivers perform in-place transforms on data held contiguously in memory using a fixed scaling factor; these are simpler to use and are sufficient for many problems. The expert drivers offer greater flexibility by including a number of additional arguments. These allow you to control: the scaling factor applied; whether the result should be output to a separate vector; the increments used in storing successive elements of a given sequence (for both input and output sequences); and the increments used in storing corresponding elements in successive sequences (for both input and output).

## ZFFT1M Routine Documentation

ZFFT1M (*MODE*,*M*,*N*,*X*,*COMM*,*INFO*)

[SUBROUTINE]

INTEGER *MODE*

[Input]

The value of *MODE* on input determines the operation performed by ZFFT1M.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : forward transforms are performed. Initializations are assumed to have been performed by a prior call to ZFFT1M.
- *MODE*=1 : backward (reverse) transforms are performed. Initializations are assumed to have been performed by a prior call to ZFFT1M.
- *MODE*=-2 : (default) initializations and forward transforms are performed.
- *MODE*=2 : (default) initializations and backward transforms are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

INTEGER *M*

[Input]

On input: *M* is the number of sequences to be transformed.

INTEGER *N*

[Input]

On input: *N* is the length of the complex sequences in *X*

COMPLEX\*16 *X*(*N*\**M*)

[Input/Output]

On input: *X* contains the *M* complex sequences of length *N* to be transformed.

Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.

On output: *X* contains the transformed sequences.

COMPLEX\*16 *COMM*(3\*N+100)

[Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO*

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
CALL ZFFT1M(0,1,N,X,COMM,INFO)
CALL ZFFT1M(-1,2,N,X,COMM,INFO)
DO 10 I = 1, N
    X(I,3) = X(I,1)*DCONJG(X(I,2))
    X(I,2) = DCMPLX(0.0D0,1.0D0)*X(I,2)
10  CONTINUE
CALL ZFFT1M(1,2,N,X(1,2),COMM,INFO)
```



## CFFT1M Routine Documentation

CFFT1M (*MODE*,*M*,*N*,*X*,*COMM*,*INFO*)

[SUBROUTINE]

INTEGER *MODE*

[Input]

The value of *MODE* on input determines the operation performed by CFFT1M.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : forward transforms are performed. Initializations are assumed to have been performed by a prior call to CFFT1M.
- *MODE*=1 : backward (reverse) transforms are performed. Initializations are assumed to have been performed by a prior call to CFFT1M.
- *MODE*=-2 : (default) initializations and forward transforms are performed.
- *MODE*=2 : (default) initializations and backward transforms are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

INTEGER *M*

[Input]

On input: *M* is the number of sequences to be transformed.

INTEGER *N*

[Input]

On input: *N* is the length of the complex sequences in *X*

COMPLEX *X*(*N*\**M*)

[Input/Output]

On input: *X* contains the *M* complex sequences of length *N* to be transformed.

Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.

On output: *X* contains the transformed sequences.

COMPLEX *COMM*(5\**N*+100)

[Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO*

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
      CALL CFFT1M(0,1,N,X,COMM,INFO)
      CALL CFFT1M(-1,2,N,X,COMM,INFO)
      DO 10 I = 1, N
         X(I,3) = X(I,1)*CONJG(X(I,2))
         X(I,2) = CMPLX(0.0D0,1.0D0)*X(I,2)
10    CONTINUE
      CALL CFFT1M(1,2,N,X(1,2),COMM,INFO)
```

## ZFFT1MX Routine Documentation

ZFFT1MX (*MODE,SCALE,INPL,NSEQ,N,X,INCX1,INCX2,*  
*Y,INCY1,INCY2,COMM,INFO*) [SUBROUTINE]

INTEGER MODE [Input]

The value of *MODE* on input determines the operation performed by ZFFT1MX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1MX.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT1MX.
- *MODE*=-2 : (default) initializations and a forward transform are performed.
- *MODE*=2 : (default) initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

DOUBLE PRECISION SCALE [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL INPL [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER NSEQ [Input]

On input: *NSEQ* is the number of sequences to be transformed

INTEGER N [Input]

On input: *N* is the number of elements in each sequence to be transformed

COMPLEX\*16 X(1+(N-1)\*INCX1+(NSEQ-1)\*INCX2) [Input/Output]

On input: *X* contains the *NSEQ* complex sequences of length *N* to be transformed; the *i*th element of sequence *j* is stored in  $X(1+(i-1)*INCX1+(j-1)*INCX2)$ .

On output: if *INPL* is .TRUE. then *X* contains the transformed sequences in the same locations as on input; otherwise *X* remains unchanged.

INTEGER INCX1 [Input]

On input: *INCX1* is the increment used to store successive elements of a given sequence in *X* (*INCX1*=1 for contiguous data).

Constraint: *INCX1* > 0.

INTEGER INCX2 [Input]

On input: *INCX2* is the increment used to store corresponding elements of successive sequences in *X* (*INCX2*=*N* for contiguous data).

Constraint: *INCX2* > 0.

COMPLEX\*16 Y(1+(N-1)\*INCY1+(NSEQ-1)\*INCY2) [Output]

On output: if *INPL* is .FALSE. then *Y* contains the transformed sequences with the *i*th element of sequence *j* stored in *Y*(1+(*i*-1)\**INCY1*+(*j*-1)\**INCY2*); otherwise *Y* is not referenced.

INTEGER INCY1 [Input]

On input: *INCY1* is the increment used to store successive elements of a given sequence in *Y*. If *INPL* is .TRUE. then *INCY1* is not referenced.

Constraint: *INCY1* > 0.

INTEGER INCY2 [Input]

On input: *INCY2* is the increment used to store corresponding elements of successive sequences in *Y* (*INCY2*=*N* for contiguous data). If *INPL* is .TRUE. then *INCY2* is not referenced.

Constraint: *INCY2* > 0.

COMPLEX\*16 COMM(3\*N+100) [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
C      Forward FFTs are performed unscaled and in-place on two
C      contiguous vectors stored in the first two columns of X.
C      Manipulations are stored in 2nd and 3rd columns of X which are
C      then transformed back.
C
      COMPLEX *16 X(N,3)
      SCALE = 1.0D0
      INPL = .TRUE.
      CALL ZFFT1MX(0,SCALE,INPL,2,N,X,1,N,DUM,1,N,COMM,INFO)
      CALL ZFFT1MX(-1,SCALE,INPL,2,N,X,1,N,DUM,1,N,COMM,INFO)
      DO 10 I = 1, N
          X(I,3) = X(I,1)*DCONJG(X(I,2))/DBLE(N)
          X(I,2) = DCMLPX(0.0D0,1.0D0)*X(I,2)/DBLE(N)
10  CONTINUE
      CALL ZFFT1MX(1,SCALE,INPL,2,N,X(1,2),1,N,DUM,1,N,COMM,INFO)
```

**CFFT1MX Routine Documentation**

CFFT1MX (*MODE,SCALE,INPL,NSEQ,N,X,INCX1,INCX2,* [SUBROUTINE]  
*Y,INCY1,INCY2,COMM,INFO*)

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by CFFT1MX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1MX.
- *MODE*=1 : a backward (reverse) transform is performed. Initializations are assumed to have been performed by a prior call to CFFT1MX.
- *MODE*=-2 : (default) initializations and a forward transform are performed.
- *MODE*=2 : (default) initializations and a backward transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

REAL *SCALE* [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL *INPL* [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER *NSEQ* [Input]

On input: *NSEQ* is the number of sequences to be transformed

INTEGER *N* [Input]

On input: *N* is the number of elements in each sequence to be transformed

COMPLEX *X*(1+(*N*-1)\**INCX1*+(*NSEQ*-1)\**INCX2*) [Input/Output]

On input: *X* contains the *NSEQ* complex sequences of length *N* to be transformed; the *i*th element of sequence *j* is stored in *X*(1+(*i*-1)\**INCX1*+(*j*-1)\**INCX2*).

On output: if *INPL* is .TRUE. then *X* contains the transformed sequences in the same locations as on input; otherwise *X* remains unchanged.

INTEGER *INCX1* [Input]

On input: *INCX1* is the increment used to store successive elements of a given sequence in *X* (*INCX1*=1 for contiguous data).

Constraint: *INCX1* > 0.

INTEGER INCX2 [Input]

On input: *INCX2* is the increment used to store corresponding elements of successive sequences in *X* (*INCX2*=*N* for contiguous data).

Constraint: *INCX2* > 0.

COMPLEX Y(1+(*N*-1)\**INCY1*+(*NSEQ*-1)\**INCY2*) [Output]

On output: if *INPL* is .FALSE. then *Y* contains the transformed sequences with the *i*th element of sequence *j* stored in *Y*(1+(*i*-1)\**INCY1*+(*j*-1)\**INCY2*); otherwise *Y* is not referenced.

INTEGER INCY1 [Input]

On input: *INCY1* is the increment used to store successive elements of a given sequence in *Y*. If *INPL* is .TRUE. then *INCY1* is not referenced.

Constraint: *INCY1* > 0.

INTEGER INCY2 [Input]

On input: *INCY2* is the increment used to store corresponding elements of successive sequences in *Y* (*INCY2*=*N* for contiguous data). If *INPL* is .TRUE. then *INCY2* is not referenced.

Constraint: *INCY2* > 0.

COMPLEX COMM(5\*N+100) [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
C      Forward FFTs are performed unscaled and in-place on two
C      contiguous vectors stored in the first two columns of X.
C      Manipulations are stored in 2nd and 3rd columns of X which are
C      then transformed back.
C
      COMPLEX X(N,3)
      SCALE = 1.0
      INPL = .TRUE.
      CALL CFFT1MX(0,SCALE,INPL,2,N,X,1,N,DUM,1,N,COMM,INFO)
      CALL CFFT1MX(-1,SCALE,INPL,2,N,X,1,N,DUM,1,N,COMM,INFO)
      DO 10 I = 1, N
          X(I,3) = X(I,1)*CONJG(X(I,2))/REAL(N)
          X(I,2) = CMPLX(0.0D0,1.0D0)*X(I,2)/REAL(N)
10    CONTINUE
      CALL CFFT1MX(1,SCALE,INPL,2,N,X(1,2),1,N,DUM,1,N,COMM,INFO)
```

### 5.2.3 2D FFT of two-dimensional arrays of data

The routines documented here compute the two-dimensional discrete Fourier transforms (DFT) of a two-dimensional array of complex numbers in either single or double precision arithmetic. The 2D DFT is computed using a highly-efficient FFT algorithm.

There are two sets of interfaces available: simple drivers and expert drivers. The simple drivers perform in-place transforms on data held contiguously in memory using a fixed scaling factor; these are simpler to use and are sufficient for many problems. The expert drivers offer greater flexibility by including a number of additional arguments. These allow you to control: the scaling factor applied; whether the result should be output to a separate array; the increments used in storing successive elements in each dimension (for both input and output); and the facility to not perform a final transposition. This final facility is useful for those cases where a forward and backward transform are to be applied with some data manipulations in between; here two whole transpositions can be saved.

## ZFFT2D Routine Documentation

ZFFT2D (*MODE,M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the direction of transform to be performed by ZFFT2D.

On input:

- *MODE*=-1 : forward 2D transform is performed.
- *MODE*=1 : backward (reverse) 2D transform is performed.

INTEGER *M* [Input]

On input: *M* is the number of rows in the 2D array of data to be transformed. If *X* is declared as a 2D array then *M* is the first dimension of *X*.

INTEGER *N* [Input]

On input: *N* is the number of columns in the 2D array of data to be transformed. If *X* is declared as a 2D array then *M* is the second dimension of *X*.

COMPLEX\*16 *X*(*M*\**N*) [Input/Output]

On input: *X* contains the *M* by *N* complex 2D array to be transformed. Element *ij* is stored in location  $i + (j - 1) * M$  of *X*.

On output: *X* contains the transformed sequence.

COMPLEX\*16 *COMM*(*M*\**N*+3\*(*M*+*N*)) [Input/Output]

*COMM* is a communication array used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

      CALL ZFFT2D(-1,M,N,X,COMM,INFO)
      DO 20 J = 1, N
        DO 10 I = 1, MIN(J-1,M)
          X(I,J) = 0.5D0*(X(I,J) + X(J,I))
          X(J,I) = DCONJG(X(I,J))
10      CONTINUE
20      CONTINUE
      CALL ZFFT2D(1,M,N,X,COMM,INFO)

```



## CFFT2D Routine Documentation

CFFT2D (*MODE,M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the direction of transform to be performed by CFFT2D.

On input:

- *MODE*=-1 : a forward 2D transform is performed.
- *MODE*=1 : a backward (reverse) 2D transform is performed.

INTEGER *M* [Input]

On input: *M* is the number of rows in the 2D array of data to be transformed. If *X* is declared as a 2D array then *M* is the first dimension of *X*.

INTEGER *N* [Input]

On input: *N* is the number of columns in the 2D array of data to be transformed. If *X* is declared as a 2D array then *M* is the second dimension of *X*.

COMPLEX *X*(*M*\**N*) [Input/Output]

On input: *X* contains the *M* by *N* complex 2D array to be transformed. Element *ij* is stored in location  $i + (j - 1) * M$  of *X*.

On output: *X* contains the transformed sequence.

COMPLEX *COMM*(*M*\**N*+5\*(*M*+*N*)) [Input/Output]

*COMM* is a communication array used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

      CALL CFFT2D(-1,M,N,X,COMM,INFO)
      DO 20 J = 1, N
        DO 10 I = 1, MIN(J-1,M)
          X(I,J) = 0.5D0*(X(I,J) + X(J,I))
          X(J,I) = CONJG(X(I,J))
10      CONTINUE
20      CONTINUE
      CALL CFFT2D(1,M,N,X,COMM,INFO)

```

## ZFFT2DX Routine Documentation

ZFFT2DX (*MODE,SCALE,LTRANS,INPL,M,N,X,INCX1,*  
*INCX2,Y,INCY1,INCY2,COMM,INFO*) [SUBROUTINE]

INTEGER MODE [Input]

The value of *MODE* on input determines the operation performed by ZFFT2DX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward 2D transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT2DX.
- *MODE*=1 : a backward (reverse) 2D transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT2DX.
- *MODE*=-2 : (default) initializations and a forward 2D transform are performed.
- *MODE*=2 : (default) initializations and a backward 2D transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the values of *N* and *M*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the values of *N* and *M*.

DOUBLE PRECISION SCALE [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL LTRANS [Input]

On input: if *LTRANS* is .TRUE. then a normal final transposition is performed internally to return transformed data consistent with the values for arguments *INPL*, *INCX1*, *INCX2*, *INCY1* and *INCY2*. If *LTRANS* is .FALSE. then the final transposition is not performed explicitly; the storage format on output is determined by whether the output data is stored contiguously or not – please see the output specifications for *X* and *Y* for details.

LOGICAL INPL [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER M [Input]

On input: *M* is the first dimension of the 2D transform.

INTEGER N [Input]

On input: *N* is the second dimension of the 2D transform.

**COMPLEX\*16**  $X(1+(M-1)*INCX1+(N-1)*INCX2)$  [Input/Output]

On input:  $X$  contains the  $M$  by  $N$  complex 2D data array to be transformed; the  $(ij)$ th element is stored in  $X(1+(i-1)*INCX1+(j-1)*INCX2)$ .

On output: if  $INPL$  is `.TRUE.` then  $X$  contains the transformed data, either in the same locations as on input when  $LTRANS=.TRUE.$ ; in locations  $X((i-1)*N+j)$  when  $LTRANS=.FALSE.$ ,  $INCX1=1$  and  $INCX2=M$ ; and otherwise in the same locations as on input. If  $INPL$  is `.FALSE.`  $X$  remains unchanged.

**INTEGER**  $INCX1$  [Input]

On input:  $INCX1$  is the increment used to store, in  $X$ , successive elements in the first dimension ( $INCX1=1$  for contiguous data).

Constraint:  $INCX1 > 0$ .

**INTEGER**  $INCX2$  [Input]

On input:  $INCX2$  is the increment used to store, in  $X$ , successive elements in the second dimension ( $INCX2=M$  for contiguous data).

Constraint:  $INCX2 > 0$ .

**COMPLEX\*16**  $Y(1+(M-1)*INCY1+(N-1)*INCY2)$  [Output]

On output: if  $INPL$  is `.FALSE.` then  $Y$  contains the transformed data. If  $LTRANS=.TRUE.$  then the  $(ij)$ th data element is stored in  $Y(1+(i-1)*INCY1+(j-1)*INCY2)$ ; if  $LTRANS=.FALSE.$ ,  $INCY1=1$  and  $INCY2=M$  then the  $(ij)$ th data element is stored in  $Y((i-1)*N+j)$ ; and otherwise the  $(ij)$ th element is stored in  $Y(1+(i-1)*INCY1+(j-1)*INCY2)$ . If  $INPL$  is `.TRUE.` then  $Y$  is not referenced.

**INTEGER**  $INCY1$  [Input]

On input:  $INCY1$  is the increment used to store successive elements in the first dimension in  $Y$  ( $INCY1=1$  for contiguous data). If  $INPL$  is `.TRUE.` then  $INCY1$  is not referenced.

Constraint:  $INCY1 > 0$ .

**INTEGER**  $INCY2$  [Input]

On input:  $INCY2$  is the increment used to store successive elements in the second dimension in  $Y$  ( $INCY2=M$  for contiguous data). If  $INPL$  is `.TRUE.` then  $INCY2$  is not referenced.

Constraint:  $INCY2 > 0$ .

**COMPLEX\*16**  $COMM(M*N+3*M+3*N+200)$  [Input/Output]

$COMM$  is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same dimensions  $M$  and  $N$ . The remainder is used as temporary store.

**INTEGER**  $INFO$  [Output]

On output:  $INFO$  is an error indicator. On successful exit,  $INFO$  contains 0. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```

C      Forward 2D FFT is performed unscaled, without final transpose
C      and out-of-place on data stored in array X and output to Y.
C      Manipulations are stored in vector Y which is then transformed
C      back, with scaling, into the first M rows of X.
C
      COMPLEX *16 X(LDX,N), Y(M*N)
      SCALE = 1.0D0
      INPL = .FALSE.
      LTRANS = .FALSE.
      CALL ZFFT2DX(0,SCALE,LTRANS,INPL,M,N,X,1,LDX,Y,1,M,COMM,INFO)
      CALL ZFFT2DX(-1,SCALE,LTRANS,INPL,M,N,X,1,LDX,Y,1,M,COMM,INFO)
      IY = 1
      DO 20 I = M
        DO 10 J = 1, N
          Y(IY) = 0.5D0*Y(IY)*EXP(0.001D0*(I+J-2))
          IY = IY + 1
10      CONTINUE
20    CONTINUE
      SCALE = 1.0D0/DBLE(M*N)
      CALL ZFFT2DX(1,SCALE,LTRANS,INPL,N,M,Y,1,N,X,1,LDX,COMM,INFO)

```

## CFFT2DX Routine Documentation

CFFT2DX (*MODE,SCALE,LTRANS,INPL,M,N,X,INCX1,*  
*INCX2,Y,INCY1,INCY2,COMM,INFO*) [SUBROUTINE]

INTEGER MODE [Input]

The value of *MODE* on input determines the operation performed by CFFT2DX.

On input:

- *MODE*=0 : only initializations (specific to the value of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=-1 : a forward 2D transform is performed. Initializations are assumed to have been performed by a prior call to CFFT2DX.
- *MODE*=1 : a backward (reverse) 2D transform is performed. Initializations are assumed to have been performed by a prior call to CFFT2DX.
- *MODE*=-2 : (default) initializations and a forward 2D transform are performed.
- *MODE*=2 : (default) initializations and a backward 2D transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the values of *N* and *M*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the values of *N* and *M*.

REAL SCALE [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL LTRANS [Input]

On input: if *LTRANS* is .TRUE. then a normal final transposition is performed internally to return transformed data consistent with the values for arguments *INPL*, *INCX1*, *INCX2*, *INCY1* and *INCY2*. If *LTRANS* is .FALSE. then the final transposition is not performed explicitly; the storage format on output is determined by whether the output data is stored contiguously or not – please see the output specifications for *X* and *Y* for details.

LOGICAL INPL [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER M [Input]

On input: *M* is the first dimension of the 2D transform.

INTEGER N [Input]

On input: *N* is the second dimension of the 2D transform.

**COMPLEX**  $X(1+(M-1)*INCX1+(N-1)*INCX2)$  [Input/Output]

On input:  $X$  contains the  $M$  by  $N$  complex 2D data array to be transformed; the  $(ij)$ th element is stored in  $X(1+(i-1)*INCX1+(j-1)*INCX2)$ .

On output: if  $INPL$  is `.TRUE.` then  $X$  contains the transformed data, either in the same locations as on input when  $LTRANS=.TRUE.$ ; in locations  $X((i-1)*N+j)$  when  $LTRANS=.FALSE.$ ,  $INCX1=1$  and  $INCX2=M$ ; and otherwise in the same locations as on input. If  $INPL$  is `.FALSE.`  $X$  remains unchanged.

**INTEGER**  $INCX1$  [Input]

On input:  $INCX1$  is the increment used to store, in  $X$ , successive elements in the first dimension ( $INCX1=1$  for contiguous data).

Constraint:  $INCX1 > 0$ .

**INTEGER**  $INCX2$  [Input]

On input:  $INCX2$  is the increment used to store, in  $X$ , successive elements in the second dimension ( $INCX2=M$  for contiguous data).

Constraint:  $INCX2 > 0$ .

**COMPLEX**  $Y(1+(M-1)*INCY1+(N-1)*INCY2)$  [Output]

On output: if  $INPL$  is `.FALSE.` then  $Y$  contains the transformed data. If  $LTRANS=.TRUE.$  then the  $(ij)$ th data element is stored in  $Y(1+(i-1)*INCY1+(j-1)*INCY2)$ ; if  $LTRANS=.FALSE.$ ,  $INCY1=1$  and  $INCY2=M$  then the  $(ij)$ th data element is stored in  $Y((i-1)*N+j)$ ; and otherwise the  $(ij)$ th element is stored in  $Y(1+(i-1)*INCY1+(j-1)*INCY2)$ . If  $INPL$  is `.TRUE.` then  $Y$  is not referenced.

**INTEGER**  $INCY1$  [Input]

On input:  $INCY1$  is the increment used to store successive elements in the first dimension in  $Y$  ( $INCY1=1$  for contiguous data). If  $INPL$  is `.TRUE.` then  $INCY1$  is not referenced.

Constraint:  $INCY1 > 0$ .

**INTEGER**  $INCY2$  [Input]

On input:  $INCY2$  is the increment used to store successive elements in the second dimension in  $Y$  ( $INCY2=M$  for contiguous data). If  $INPL$  is `.TRUE.` then  $INCY2$  is not referenced.

Constraint:  $INCY2 > 0$ .

**COMPLEX**  $COMM(M*N+5*M+5*N+200)$  [Input/Output]

$COMM$  is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same dimensions  $M$  and  $N$ . The remainder is used as temporary store.

**INTEGER**  $INFO$  [Output]

On output:  $INFO$  is an error indicator. On successful exit,  $INFO$  contains 0. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```
C      Forward 2D FFT is performed unscaled, without final transpose
C      and out-of-place on data stored in array X and output to Y.
C      Manipulations are stored in vector Y which is then transformed
C      back, with scaling, into the first M rows of X.
C
      COMPLEX X(LDX,N), Y(M*N)
      SCALE = 1.0
      INPL = .FALSE.
      LTRANS = .FALSE.
      CALL CFFT2DX(0,SCALE,LTRANS,INPL,M,N,X,1,LDX,Y,1,M,COMM,INFO)
      CALL CFFT2DX(-1,SCALE,LTRANS,INPL,M,N,X,1,LDX,Y,1,M,COMM,INFO)
      IY = 1
      DO 20 I = M
        DO 10 J = 1, N
          Y(IY) = 0.5*Y(IY)*EXP(-0.001*REAL(I+J-2))
          IY = IY + 1
10      CONTINUE
20    CONTINUE
      SCALE = 1.0/REAL(M*N)
      CALL CFFT2DX(1,SCALE,LTRANS,INPL,N,M,Y,1,N,X,1,LDX,COMM,INFO)
```

### 5.2.4 3D FFT of three-dimensional arrays of data

The routines documented here compute the three-dimensional discrete Fourier transforms (DFT) of a three-dimensional array of complex numbers in either single or double precision arithmetic. The 3D DFT is computed using a highly-efficient FFT algorithm.

Please note that at Release 2.7 of ACML it has been necessary to modify slightly the interfaces of two of the expert FFT drivers introduced at Release 2.2 of ACML. The two routines are `CFFT3DX` and `ZFFT3DX`. The changes are required to permit the optimization of these routines by adding an initialization stage which can then use the plan generator (`MODE=100`) to select the optimal plan. User codes that called `CFFT3DX` or `ZFFT3DX` using a release of ACML prior to 2.7 will need to be modified in one of two ways. Calls to `CFFT3DX/ZFFT3DX` with `MODE = -1` or `1` can be fixed for ACML Release 2.7 and later by either:

- preceding the call with a call setting `MODE = 0` (default initialization), or `MODE = 100` (initialization using plan generator); or,
- doubling the `MODE` argument value to `MODE = -2` or `2` respectively (thus incorporating default initialization).

Additionally, the minimum length of the communication (work)space arrays in `CFFT3DX` and `ZFFT3DX` has been increased by 100 to allow for plan storage. Please consult the individual routine documents for full details on their use.



## ZFFT3D Routine Documentation

ZFFT3D (*MODE,L,M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the direction of transform to be performed by ZFFT3D.

On input:

- *MODE*=-1 : forward 3D transform is performed.
- *MODE*=1 : backward (reverse) 3D transform is performed.

INTEGER *L* [Input]

On input: the length of the first dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *L* is the first dimension of *X*.

INTEGER *M* [Input]

On input: the length of the second dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *M* is the second dimension of *X*.

INTEGER *N* [Input]

On input: the length of the third dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *N* is the third dimension of *X*.

COMPLEX\*16 *X*(*L\*M\*N*) [Input/Output]

On input: *X* contains the *L* by *M* by *N* complex 3D array to be transformed. Element *ijk* is stored in location  $i + (j - 1) * L + (k - 1) * L * M$  of *X*.

On output: *X* contains the transformed sequence.

COMPLEX\*16 *COMM*(*L\*M\*N+3\*(L+M+N)*) [Input/Output]

*COMM* is a communication array used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

CALL ZFFT3D(-1,L,M,N,X,COMM,INFO)
DO 30 K = 1, N
  DO 20 J = 1, M
    DO 10 I = 1, L
      X(I,J) = X(I,J)*EXP(-0.001D0*DBLE(I+J+K))
10    CONTINUE
20  CONTINUE
30  CONTINUE
CALL ZFFT3D(1,L,M,N,X,COMM,INFO)

```

## CFFT3D Routine Documentation

CFFT3D (*MODE,L,M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the direction of transform to be performed by CFFT3D.

On input:

- *MODE*=-1 : forward 3D transform is performed.
- *MODE*=1 : backward (reverse) 3D transform is performed.

INTEGER *L* [Input]

On input: the length of the first dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *L* is the first dimension of *X*.

INTEGER *M* [Input]

On input: the length of the second dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *M* is the second dimension of *X*.

INTEGER *N* [Input]

On input: the length of the third dimension of the 3D array of data to be transformed. If *X* is declared as a 3D array then *N* is the third dimension of *X*.

COMPLEX *X*(*L\*M\*N*) [Input/Output]

On input: *X* contains the *L* by *M* by *N* complex 3D array to be transformed. Element *ijk* is stored in location  $i + (j - 1) * L + (k - 1) * L * M$  of *X*.

On output: *X* contains the transformed sequence.

COMPLEX *COMM*(*L\*M\*N+5\*(L+M+N)*) [Input/Output]

*COMM* is a communication array used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

CALL CFFT3D(-1,L,M,N,X,COMM,INFO)
DO 30 K = 1, N
  DO 20 J = 1, M
    DO 10 I = 1, L
      X(I,J) = X(I,J)*EXP(-0.001D0*REAL(I+J+K))
10    CONTINUE
20  CONTINUE
30  CONTINUE
CALL CFFT3D(1,L,M,N,X,COMM,INFO)

```

**ZFFT3DX Routine Documentation**

ZFFT3DX (*MODE,SCALE,LTRANS,INPL,L,M,N,X,Y,* [SUBROUTINE]  
*COMM,INFO*)

INTEGER MODE [Input]

The value of *MODE* on input determines the operation performed by ZFFT3DX.

On input:

- *MODE*=0 : only initializations (specific to the values of *L*, *M* and *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=−1 or 1.
- *MODE*=−1 : a forward 2D transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT3DX.
- *MODE*=1 : a backward (reverse) 2D transform is performed. Initializations are assumed to have been performed by a prior call to ZFFT3DX.
- *MODE*=−2 : (default) initializations and a forward 2D transform are performed.
- *MODE*=2 : (default) initializations and a backward 2D transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the values of *L*, *M* and *M*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the values of *L*, *M* and *N*.

DOUBLE PRECISION SCALE [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL LTRANS [Input]

On input: if *LTRANS* is .TRUE. then a normal final transposition is performed internally to return transformed data using the same storage format as the input data. If *LTRANS* is .FALSE. then the final transposition is not performed and transformed data is stored, in *X* or *Y*, in transposed form.

LOGICAL INPL [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER L [Input]

On input: *L* is the first dimension of the 3D transform.

INTEGER M [Input]

On input: *M* is the second dimension of the 3D transform.

INTEGER N [Input]

On input: *N* is the third dimension of the 3D transform.

**COMPLEX\*16 X(L\*M\*N)** [Input/Output]

On input: *X* contains the *L* by *M* by *N* complex 3D data array to be transformed; the (ijk)th element is stored in  $X(i+(j-1)*L+(k-1)*L*M)$ .

On output: if *INPL* is .TRUE. then *X* contains the transformed data, either in the same locations as on input when *LTRANS*=.TRUE.; or in locations  $X(k+(j-1)*N+(i-1)*N*M)$  when *LTRANS*=.FALSE. If *INPL* is .FALSE. *X* remains unchanged.

**COMPLEX\*16 Y(L\*M\*N)** [Output]

On output: if *INPL* is .FALSE. then *Y* contains the three-dimensional transformed data. If *LTRANS*=.TRUE. then the (ijk)th data element is stored in  $Y(i+(j-1)*L+(k-1)*L*M)$ ; otherwise, the (ijk)th data element is stored in  $Y(k+(j-1)*N+(i-1)*N*M)$ . If *INPL* is .TRUE. then *Y* is not referenced.

**COMPLEX\*16 COMM(L\*M\*N+5\*(L+M+N)+300)** [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence dimensions. The remainder is used as temporary store.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

C      Forward 3D FFT is performed unscaled, without final transpose
C      and out-of-place on data stored in array X and output to Y.
C      Manipulations are stored in vector Y which is then transformed
C      back, with scaling, into the first M rows of X.
C
      COMPLEX *16 X(L*M*N), Y(L*M*N)
      SCALE = 1.0D0
      INPL = .FALSE.
      LTRANS = .FALSE.
      CALL ZFFT3DX(0,SCALE,LTRANS,INPL,L,M,N,X,Y,COMM,INFO)
      CALL ZFFT3DX(-1,SCALE,LTRANS,INPL,L,M,N,X,Y,COMM,INFO)
      IY = 1
      DO 20 I = 1, L
        DO 40 J = 1, M
          DO 10 K = 1, N
            Y(IY) = Y(IY)*EXP(-0.001D0*DBLE(I+J+K-3))
            IY = IY + 1
          10      CONTINUE
        20      CONTINUE
      SCALE = 1.0D0/DBLE(L*M*N)
      CALL ZFFT3DX(1,SCALE,LTRANS,INPL,N,M,L,Y,X,COMM,INFO)

```

**CFFT3DX Routine Documentation**

CFFT3DX (*MODE,SCALE,LTRANS,INPL,L,M,N,X,Y,* [SUBROUTINE]  
*COMM,INFO*)

INTEGER MODE [Input]

The value of *MODE* on input determines the operation performed by CFFT3DX.

On input:

- *MODE*=0 : only initializations (specific to the values of *L*, *M* and *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=−1 or 1.
- *MODE*=−1 : a forward 2D transform is performed. Initializations are assumed to have been performed by a prior call to CFFT3DX.
- *MODE*=1 : a backward (reverse) 2D transform is performed. Initializations are assumed to have been performed by a prior call to CFFT3DX.
- *MODE*=−2 : (default) initializations and a forward 2D transform are performed.
- *MODE*=2 : (default) initializations and a backward 2D transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the values of *L*, *M* and *M*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the values of *L*, *M* and *N*.

REAL SCALE [Input]

On input: *SCALE* is the scaling factor to apply to the output sequences

LOGICAL LTRANS [Input]

On input: if *LTRANS* is .TRUE. then a normal final transposition is performed internally to return transformed data using the same storage format as the input data. If *LTRANS* is .FALSE. then the final transposition is not performed and transformed data is stored, in *X* or *Y*, in transposed form.

LOGICAL INPL [Input]

On input: if *INPL* is .TRUE. then *X* is overwritten by the output sequences; otherwise the output sequences are returned in *Y*.

INTEGER L [Input]

On input: *L* is the first dimension of the 3D transform.

INTEGER M [Input]

On input: *M* is the second dimension of the 3D transform.

INTEGER N [Input]

On input: *N* is the third dimension of the 3D transform.

**COMPLEX X(L\*M\*N)** [Input/Output]

On input: *X* contains the *L* by *M* by *N* complex 3D data array to be transformed; the (ijk)th element is stored in  $X(i+(j-1)*L+(k-1)*L*M)$ .

On output: if *INPL* is .TRUE. then *X* contains the transformed data, either in the same locations as on input when *LTRANS*=.TRUE.; or in locations  $X(k+(j-1)*N+(i-1)*N*M)$  when *LTRANS*=.FALSE. If *INPL* is .FALSE. *X* remains unchanged.

**COMPLEX Y(L\*M\*N)** [Output]

On output: if *INPL* is .FALSE. then *Y* contains the three-dimensional transformed data. If *LTRANS*=.TRUE. then the (ijk)th data element is stored in  $Y(i+(j-1)*L+(k-1)*L*M)$ ; otherwise, the (ijk)th data element is stored in  $Y(k+(j-1)*N+(i-1)*N*M)$ . If *INPL* is .TRUE. then *Y* is not referenced.

**COMPLEX COMM(L\*M\*N+5\*(L+M+N)+300)** [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence dimensions. The remainder is used as temporary store.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

C      Forward 3D FFT is performed unscaled, without final transpose
C      and out-of-place on data stored in array X and output to Y.
C      Manipulations are stored in vector Y which is then transformed
C      back, with scaling, into the first M rows of X.
C
      SCALE = 1.0
      INPL = .FALSE.
      LTRANS = .FALSE.
      CALL CFFT3DX(0,SCALE,LTRANS,INPL,L,M,N,X,Y,COMM,INFO)
      CALL CFFT3DX(-1,SCALE,LTRANS,INPL,L,M,N,X,Y,COMM,INFO)
      IY = 1
      DO 20 I = 1, L
        DO 40 J = 1, M
          DO 10 K = 1, N
            Y(IY) = Y(IY)*EXP(-0.001*REAL(I+J+K-3))
            IY = IY + 1
          10    CONTINUE
        20    CONTINUE
      SCALE = 1.0/REAL(L*M*N)
      CALL CFFT3DX(1,SCALE,LTRANS,INPL,N,M,L,Y,X,COMM,INFO)

```

### 5.3 FFTs on real and Hermitian data sequences

The routines documented here compute discrete Fourier transforms (DFTs) of sequences of real numbers or of Hermitian sequences in either single or double precision arithmetic. The DFTs are computed using a highly-efficient FFT algorithm. Hermitian sequences are represented in a condensed form that is described in [Section 5.1 \[Introduction to FFTs\]](#), [page 21](#). The DFT of a real sequence results in a Hermitian sequence; the DFT of a Hermitian sequence is a real sequence.

Please note that prior to Release 2.0 of ACML the routine ZDFFT/CSFFT and ZDFFTM/CSFFTM returned results that were scaled by a factor 0.5 compared with the currently returned results.

### 5.3.1 FFT of single sequences of real data

#### DZFFT Routine Documentation

DZFFT (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by DZFFT.

On input:

- *MODE*=0 : only default initializations (specific to *N*) are performed; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=1 : a real transform is performed. Initializations are assumed to have been performed by a prior call to DZFFT.
- *MODE*=2 : (default) initializations and a real transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations are performed, but first a plan is generated. This plan is chosen based on the fastest FFT computation for a subset of all possible plans.

INTEGER *N* [Input]

On input: *N* is the length of the real sequence *X*

DOUBLE PRECISION *X(N)* [Input/Output]

On input: *X* contains the real sequence of length *N* to be transformed.

On output: *X* contains the transformed Hermitian sequence.

DOUBLE PRECISION *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

      CALL DZFFT(0,N,X,COMM,INFO)
      CALL DZFFT(1,N,X,COMM,INFO)
      DO 10 I = N/2+2, N
         X(I) = -X(I)
10    CONTINUE
      CALL DZFFT(1,N,X,COMM,INFO)

```



## SCFFT Routine Documentation

SCFFT (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by SCFFT.

On input:

- *MODE*=0 : only default initializations (specific to *N*) are performed; this is usually followed by calls to the same routine with *MODE*=-1 or 1.
- *MODE*=1 : a real transform is performed. Initializations are assumed to have been performed by a prior call to SCFFT.
- *MODE*=2 : (default) initializations and a real transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations are performed, but first a plan is generated. This plan is chosen based on the fastest FFT computation for a subset of all possible plans.

INTEGER *N* [Input]

On input: *N* is the length of the real sequence *X*

REAL *X(N)* [Input/Output]

On input: *X* contains the real sequence of length *N* to be transformed.

On output: *X* contains the transformed Hermitian sequence.

REAL *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

CALL SCFFT(0,N,X,COMM,INFO)
CALL SCFFT(1,N,X,COMM,INFO)
DO 10 I = N/2+2, N
    X(I) = -X(I)
10 CONTINUE
CALL CSFFT(1,N,X,COMM,INFO)
```

### 5.3.2 FFT of multiple sequences of real data

#### DZFFTM Routine Documentation

DZFFTM (*M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *M* [Input]

On input: *M* is the number of sequences to be transformed.

INTEGER *N* [Input]

On input: *N* is the length of the real sequences in *X*

DOUBLE PRECISION *X(N\*M)* [Input/Output]

On input: *X* contains the *M* real sequences of length *N* to be transformed.

Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.

On output: *X* contains the transformed Hermitian sequences.

DOUBLE PRECISION *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

      CALL DZFFTM(1,N,X,COMM,INFO)
      CALL DZFFTM(2,N,X,COMM,INFO)
      DO 10 I = 1, N
         X(I,3) = X(I,1)*X(N-I+1,2)
10    CONTINUE
      CALL ZDFFTM(1,N,X(1,3),COMM,INFO)

```

**SCFFTM Routine Documentation****SCFFTM** (*M,N,X,COMM,INFO*) [SUBROUTINE]INTEGER *M* [Input]On input: *M* is the number of sequences to be transformed.INTEGER *N* [Input]On input: *N* is the length of the real sequences in *X*REAL *X*(*N*\**M*) [Input/Output]On input: *X* contains the *M* real sequences of length *N* to be transformed.  
Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.On output: *X* contains the transformed Hermitian sequences.REAL *COMM*(3\*N+100) [Input/Output]*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.INTEGER *INFO* [Output]On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.  
If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

      CALL SCFFTM(1,N,X,COMM,INFO)
      CALL SCFFTM(2,N,X,COMM,INFO)
      DO 10 I = 1, N
         X(I,3) = X(I,1)*X(N-I+1,2)
10    CONTINUE
      CALL CSFFTM(1,N,X(1,3),COMM,INFO)

```

### 5.3.3 FFT of single Hermitian sequences

#### ZDFFT Routine Documentation

ZDFFT (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by ZDFFT.

On input:

- *MODE*=0 : only initializations (specific to the values of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=1.
- *MODE*=1 : a real transform is performed. Initializations are assumed to have been performed by a prior call to ZDFFT.
- *MODE*=2 : (default) initializations and a real transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

INTEGER *N* [Input]

On input: *N* is length of the sequence in *X*

DOUBLE PRECISION *X(N)* [Input/Output]

On input: *X* contains the Hermitian sequence of length *N* to be transformed.

On output: *X* contains the transformed real sequence.

DOUBLE PRECISION *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

      CALL DZFFT(0,N,X,COMM,INFO)
      CALL DZFFT(1,N,X,COMM,INFO)
      DO 10 I = N/2+2, N
         X(I) = -X(I)
10    CONTINUE
      CALL ZDFFT(1,N,X,COMM,INFO)

```

## CSFFT Routine Documentation

CSFFT (*MODE,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *MODE* [Input]

The value of *MODE* on input determines the operation performed by CSFFT.

On input:

- *MODE*=0 : only initializations (specific to the values of *N*) are performed using a default plan; this is usually followed by calls to the same routine with *MODE*=1.
- *MODE*=1 : a real transform is performed. Initializations are assumed to have been performed by a prior call to CSFFT.
- *MODE*=2 : (default) initializations and a real transform are performed.
- *MODE*=100 : similar to *MODE*=0; only initializations (specific to the value of *N*) are performed, but these are based on a plan that is first generated by timing a subset of all possible plans and choosing the quickest (i.e. the FFT computation was timed as fastest based on the chosen plan). The plan generation phase may take a significant amount of time depending on the value of *N*.

INTEGER *N* [Input]

On input: *N* is the length of the sequence in *X*

REAL *X(N)* [Input/Output]

On input: *X* contains the Hermitian sequence of length *N* to be transformed.

On output: *X* contains the transformed real sequence.

REAL *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

CALL SCFFT(0,N,X,COMM,INFO)
CALL SCFFT(1,N,X,COMM,INFO)
DO 10 I = N/2+2, N
    X(I) = -X(I)
10 CONTINUE
CALL CSFFT(1,N,X,COMM,INFO)

```

### 5.3.4 FFT of multiple Hermitian sequences

#### ZDFFTM Routine Documentation

ZDFFTM (*M,N,X,COMM,INFO*) [SUBROUTINE]

INTEGER *M* [Input]

On input: *M* is the number of sequences to be transformed.

INTEGER *N* [Input]

On input: *N* is the length of the sequences in *X*

DOUBLE PRECISION *X(N\*M)* [Input/Output]

On input: *X* contains the *M* Hermitian sequences of length *N* to be transformed.

Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.

On output: *X* contains the transformed real sequences.

DOUBLE PRECISION *COMM(3\*N+100)* [Input/Output]

*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```

      CALL DZFFTM(1,N,X,COMM,INFO)
      CALL DZFFTM(2,N,X,COMM,INFO)
      DO 10 I = 1, N
         X(I,3) = X(I,1)*X(N-I+1,2)
10    CONTINUE
      CALL ZDFFTM(1,N,X(1,3),COMM,INFO)

```

**CSFFTM Routine Documentation****CSFFTM** (*M,N,X,COMM,INFO*) [SUBROUTINE]**INTEGER** *M* [Input]On input: *M* is the number of sequences to be transformed.**INTEGER** *N* [Input]On input: *N* is the length of the sequences in *X***REAL** *X(N\*M)* [Input/Output]On input: *X* contains the *M* Hermitian sequences of length *N* to be transformed.  
Element *i* of sequence *j* is stored in location  $i + (j - 1) * N$  of *X*.On output: *X* contains the transformed real sequences.**REAL** *COMM(3\*N+100)* [Input/Output]*COMM* is a communication array. Some portions of the array are used to store initializations for subsequent calls with the same sequence length *N*. The remainder is used as temporary store.**INTEGER** *INFO* [Output]On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.  
If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

      CALL SCFFTM(1,N,X,COMM,INFO)
      CALL SCFFTM(2,N,X,COMM,INFO)
      DO 10 I = 1, N
         X(I,3) = X(I,1)*X(N-I+1,2)
10    CONTINUE
      CALL CSFFTM(1,N,X(1,3),COMM,INFO)

```

## 6 Random Number Generators

Within the context of this document, a base random number generator (BRNG) is a mathematical algorithm that, given an initial state, produces a sequence (or stream) of variates (or values) uniformly distributed over the open interval  $(0,1)$ . The period of the BRNG is defined as the maximum number of values that can be generated before the sequence starts to repeat. The initial state of a BRNG is often called the seed.

A pseudo-random number generator (PRNG) is a BRNG that produces a stream of variates that are independent and statistically indistinguishable from a random sequence. A PRNG has several advantages over a true random number generator in that the generated sequence is repeatable, has known mathematical properties and is usually much quicker to generate. A quasi-random number generator (QRNG) is similar to a PRNG, however the variates generated are not statistically independent, rather they are designed to give a more even distribution in multidimensional space. Many books on statistics and computer science have good introductions to PRNGs and QRNGs, see for example Knuth [6] or Banks [7]. All of the BRNGs supplied in the ACML are PRNGs.

In addition to standard PRNGs some applications require cryptologically secure generators. A PRNG is said to be cryptologically secure if there is no polynomial-time algorithm which, on input of the first  $l$  bits of the output sequence can predict the  $(l + 1)$ st bit of the sequence with probability significantly greater than 0.5. This is equivalent to saying there exists no polynomial-time algorithm that can correctly distinguish between an output sequence from the PRNG and a truly random sequence of the same length with probability significantly greater than 0.5 [8].

A distribution generator is a routine that takes variates generated from a BRNG and transforms them into variates from a specified distribution, for example the Gaussian (Normal) distribution.

The ACML contains five base generators, (Section 6.1 [Base Generators], page 65), and twenty-three distribution generators (Section 6.3 [Distribution Generators], page 86). In addition users can supply a custom built generator as the base generator for all of the distribution generators (Section 6.1.8 [User Supplied Generators], page 75).

The base generators were tested using the Big Crush, Small Crush and Pseudo Diehard test suites from the TestU01 software library [15].

### 6.1 Base Generators

The five base generators (BRNGs) supplied with the ACML are; the NAG basic generator [9], a series of Wichmann-Hill generators [10], the Mersenne Twister [11], L'Ecuyer's combined recursive generator MRG32k3a [12] and the Blum-Blum-Shub generator [8].

If a single stream of variates is required it is recommended that the Mersenne Twister (Section 6.1.5 [Mersenne Twister], page 73) base generator is used. This generator combines speed with good statistical properties and an extremely long period. The NAG basic generator (Section 6.1.3 [Basic NAG Generator], page 72) is another quick generator suitable for generating a single stream. However it has a shorter period than the Mersenne Twister and being a linear congruential generator, its statistical properties are not as good.

If 273 or fewer multiple streams, with a period of up to  $2^{80}$  are required then it is recommended that the Wichmann-Hill generators are used (Section 6.1.4 [Wichmann-Hill



Generator], page 73). For more streams or multiple streams with a longer period it is recommended that the L'Ecuyer combined recursive generator (Section 6.1.6 [L'Ecuyer's Combined Recursive Generator], page 74) is used in combination with the skip ahead routine (Section 6.2.3 [Skip Ahead], page 80). Generating multiple streams of variates by skipping ahead is generally quicker than generating the streams using the leap frog method. More details on multiple streams can be found in Section 6.2 [Multiple Streams], page 79.

The Blum-Blum-Shub generator (Section 6.1.7 [Blum-Blum-Shub Generator], page 74) should only be used if a cryptologically secure generator is required. This generator is extremely slow and has poor statistical properties when used as a base generator for any of the distributional generators.

### 6.1.1 Initialization of the Base Generators

A random number generator must be initialized before use. Three routines are supplied within the ACML for this purpose: `DRANDINITIALIZE`, `DRANDINITIALIZEBBS` and `DRANDINITIALIZEUSER` (see [DRANDINITIALIZE], page 67, [DRANDINITIALIZEBBS], page 70 and [DRANDINITIALIZEUSER], page 76, respectively). Of these, `DRANDINITIALIZE` is used to initialize all of the supplied base generators, `DRANDINITIALIZEBBS` supplies an alternative interface to `DRANDINITIALIZE` for the Blum-Blum-Shub generator, and `DRANDINITIALIZEUSER` allows the user to register and initialize their own base generator.

Both double and single precision versions of all RNG routines are supplied. Double precision names are prefixed by `DRAND`, and single precision by `SRAND`. Note that if a generator has been initialized using the relevant double precision routine, then the double precision versions of the distribution generators must also be used, and vice versa. This even applies to generators with no double or single precision parameters; for example, a call of `DRANDDISCRETEUNIFORM` must be preceded by a call to one of the double precision initializers (typically `DRANDINITIALIZE`).

No utilities for saving, retrieving or copying the current state of a generator have been provided. All of the information on the current state of a generator (or stream, if multiple streams are being used) is stored in the integer array *STATE* and as such this array can be treated as any other integer array, allowing for easy copying, restoring etc.

The statistical properties of a sequence of random numbers are only guaranteed within the sequence, and not between sequences provided by the same generator. Therefore it is likely that repeated initialization will render the numbers obtained less, rather than more, independent. In most cases there should only be a single call to one of the initialization routines, per application, and this call must be made before any variates are generated. One example of where multiple initialization may be required is briefly touched upon in Section 6.2 [Multiple Streams], page 79.

In order to initialize the Blum-Blum-Shub generator a number of additional parameters, as well as an initial state (seed), are required. Although this generator can be initialized through the `DRANDINITIALIZE` routine it is recommended that the `DRANDINITIALIZEBBS` routine is used instead.

**DRANDINITIALIZE / SRANDINITIALIZE**

Initialize one of the five supplied base generators; NAG basic generator, Wichmann-Hill generator, Mersenne Twister, L'Ecuyer's combined recursive generator (MRG32k3a) or the Blum-Blum-Shub generator.

*(Note that SRANDINITIALIZE is the single precision version of DRANDINITIALIZE. The argument lists of both routines are identical except that any double precision arguments of DRANDINITIALIZE are replaced in SRANDINITIALIZE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDINITIALIZE** (*GENID*,*SUBID*,*SEED*,*LSEED*,*STATE*,  
*LSTATE*,*INFO*) [SUBROUTINE]

**INTEGER GENID** [Input]

On input: a numerical code indicating which of the five base generators to initialize.

- 1 = NAG basic generator (Section 6.1.3 [Basic NAG Generator], page 72).
- 2 = Wichmann-Hill generator (Section 6.1.4 [Wichmann-Hill Generator], page 73).
- 3 = Mersenne Twister (Section 6.1.5 [Mersenne Twister], page 73).
- 4 = L'Ecuyer's Combined Recursive generator (Section 6.1.6 [L'Ecuyer's Combined Recursive Generator], page 74).
- 5 = Blum-Blum-Shub generator (Section 6.1.7 [Blum-Blum-Shub Generator], page 74).

Constraint:  $1 \leq GENID \leq 5$ .

**INTEGER SUBID** [Input]

On input: if  $GENID = 2$ , then *SUBID* indicates which of the 273 Wichmann-Hill generators to use. If  $GENID = 5$  then *SUBID* indicates the number of bits to use (*v*) from each of iteration of the Blum-Blum-Shub generator. In all other cases *SUBID* is not referenced.

Constraint: If  $GENID = 2$  then  $1 \leq SUBID \leq 273$ .

**INTEGER SEED(LSEED)** [Input]

On input: if  $GENID \neq 5$ , then *SEED* is a vector of initial values for the base generator. The number of values required depends on the base generator being used. The NAG basic generator requires one initial value, the Wichmann-Hill generator requires four initial values, the L'Ecuyer combined recursive generator requires six initial values and the Mersenne Twister requires 624 initial values. If the number of seeds required by the chosen generator is  $> LSEED$  then *SEED*(1) is used to initialize the NAG basic generator. This is then used to generate all of the remaining seed values required. In general it is best not to set all the elements of *SEED* to anything too obvious, such as a single repeated value or a simple sequence. Using such a seed array may lead to several similar

values being created in a row when the generator is subsequently called. This is particularly true for the Mersenne Twister generator.

In order to initialize the Blum-Blum-Shub generator two large prime values,  $p$  and  $q$  are required as well as an initial value  $s$ . As  $p$ ,  $q$  and  $s$  can be of an arbitrary size, these values are expressed as a polynomial in  $B$ , where  $B = 2^{24}$ . For example,  $p$  can be factored into a polynomial of order  $l_p$ , with  $p = p_1 + p_2B + p_3B^2 + \cdots + p_{l_p}B^{l_p-1}$ . The elements of *SEED* should then be set to the following:

- $SEED(1) = l_p$
- $SEED(2)$  to  $SEED(l_p + 1) = p_1$  to  $p_{l_p}$
- $SEED(l_p + 2) = l_q$
- $SEED(l_p + 3)$  to  $SEED(l_p + l_q + 2) = q_1$  to  $q_{l_q}$
- $SEED(l_p + l_q + 3) = l_s$
- $SEED(l_p + l_q + 4)$  to  $SEED(l_p + l_q + l_s + 3) = s_1$  to  $s_{l_s}$

INTEGER *LSEED* [Input/Output]

On input: either the length of the seed vector, *SEED*, or a value  $\leq 0$ .

On output: if  $LSEED \leq 0$  on input, then *LSEED* is set to the number of initial values required by the selected generator, and the routine returns. Otherwise *LSEED* is left unchanged.

INTEGER *STATE*(*LSTATE*) [Output]

On output: the state vector required by all of the supplied distributional and base generators.

INTEGER *LSTATE* [Input/Output]

On input: either the length of the state vector, *STATE*, or a value  $\leq 0$ .

On output: if  $LSTATE \leq 0$  on input, then *LSTATE* is set to the minimum length of the state vector *STATE* for the base generator chosen, and the routine returns. Otherwise *LSTATE* is left unchanged.

Constraint:  $LSTATE \leq 0$  or the minimum length for the chosen base generator, given by:

- $GENID = 1$ :  $LSTATE \geq 16$ ,
- $GENID = 2$ :  $LSTATE \geq 20$ ,
- $GENID = 3$ :  $LSTATE \geq 633$ ,
- $GENID = 4$ :  $LSTATE \geq 61$ ,
- $GENID = 5$ :  $LSTATE \geq l_p + l_q + l_s + 6$ , where  $l_p$ ,  $l_q$  and  $l_s$  are the order of the polynomials used to express the parameters  $p$ ,  $q$  and  $s$  respectively.

INTEGER *INFO* [Output]

On output: *INFO* is an error indicator. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value. If  $INFO = 1$  on exit, then either, or both of *LSEED* and /

or *LSTATE* have been set to the required length for vectors *SEED* and *STATE* respectively. Of the two variables *LSEED* and *LSTATE*, only those which had an input value  $\leq 0$  will have been set. The *STATE* vector will not have been initialized. If *INFO* = 0 then the state vector, *STATE*, has been successfully initialized.

Example:

```
C      Generate 100 values from the Beta distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Beta distribution
      CALL DRANDBETA(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

## DRANDINITIALIZEBBS / SRANDINITIALIZEBBS

Alternative initialization routine for the Blum-Blum-Shub generator. Unlike the other base generators supplied with the ACML, the Blum-Blum-Shub generator requires two additional parameters,  $p$  and  $q$  as well as an initial state,  $s$ . The parameters  $p$ ,  $q$  and  $s$  can be of an arbitrary size. In order to avoid overflow these values are expressed as a polynomial in  $B$ , where  $B = 2^{24}$ . For example,  $p$  can be factored into a polynomial of order  $l_p$ , with  $p = p_1 + p_2B + p_3B^2 + \cdots + p_{l_p}B^{l_p-1}$ , similarly  $q = q_1 + q_2B + q_3B^2 + \cdots + q_{l_q}B^{l_q-1}$  and  $s = s_1 + s_2B + s_3B^2 + \cdots + s_{l_s}B^{l_s-1}$ .

(Note that *SRANDINITIALIZEBBS* is the single precision version of *DRANDINITIALIZEBBS*. The argument lists of both routines are identical except that any double precision arguments of *DRANDINITIALIZEBBS* are replaced in *SRANDINITIALIZEBBS* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

DRANDINITIALIZEBBS (NBITS,LP,P,LQ,Q,LS,S,STATE,LSTATE, [SUBROUTINE]  
INFO)

INTEGER NBITS [Input]

On input: the number of bits,  $v$ , to use from each iteration of the Blum-Blum-Shub generator. If  $NBITS < 1$  then  $NBITS = 1$ . If  $NBITS > 15$  then  $NBITS = 15$ .

INTEGER LP [Input]

On input: the order of the polynomial used to express  $p$  ( $l_p$ ).

Constraint:  $1 \leq LP \leq 25$ .

INTEGER P(LP) [Input]

On input: the coefficients of the polynomial used to express  $p$ .  $P(i) = p_i, i = 1$  to  $l_p$ .

Constraint:  $0 \leq P(i) < 2^{24}$

INTEGER LQ [Input]

On input: the order of the polynomial used to express  $q$  ( $l_q$ ).

Constraint:  $1 \leq LQ \leq 25$ .

INTEGER Q(LQ) [Input]

On input: the coefficients of the polynomial used to express  $q$ .  $Q(i) = q_i, i = 1$  to  $l_q$ .

Constraint:  $0 \leq Q(i) < 2^{24}$

INTEGER LS [Input]

On input: the order of the polynomial used to express  $s$  ( $l_s$ ).

Constraint:  $1 \leq LS \leq 25$ .

**INTEGER S(*LS*)** [Input]  
 On input: the coefficients of the polynomial used to express  $s$ .  $S(i) = s_i, i = 1$  to  $l_s$ .

Constraint:  $0 \leq S(i) < 2^{24}$

**INTEGER STATE(\*)** [Output]  
 On output: the initial state for the Blum-Blum-Shub generator with parameters  $P, Q, S$  and  $NBITS$ .

**INTEGER LSTATE** [Input/Output]  
 On input: either the length of the state vector,  $STATE$ , or a value  $\leq 0$ .

On output: if  $LSTATE \leq 0$  on input, then  $LSTATE$  is set to the minimum length of the state vector  $STATE$  for the parameters chosen, and the routine returns. Otherwise  $LSTATE$  is left unchanged.

Constraint:  $LSTATE \leq 0$  or  $LSTATE \geq l_p + l_q + l_s + 6$

**INTEGER INFO** [Output]  
 On output:  $INFO$  is an error indicator. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value. If  $INFO = 1$  on exit, then  $LSTATE$  has been set to the required length for the  $STATE$  vector. If  $INFO = 0$  then the state vector,  $STATE$ , has been successfully initialized.

### 6.1.2 Calling the Base Generators

With the exception of the Blum-Blum-Shub generator, there are no interfaces for direct access to the base generators. All of the base generators return variates uniformly distributed over the open interval  $(0, 1)$ . This functionality can be accessed using the uniform distributional generator **DRANDUNIFORM**, with parameter  $A = 0.0$  and parameter  $B = 1.0$  (see [\[DRANDUNIFORM\]](#), page 109). The base generator used is, as usual, selected during the initialization process (see [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66).

To directly access the Blum-Blum-Shub generator, use the routine **DRANDBLUMBLUMSHUB**.

**DRANDBLUMBLUMSHUB / SRANDBLUMBLUMSHUB**

Allows direct access to the bit stream generated by the Blum-Blum-Shub generator.

(Note that *SRANDBLUMBLUMSHUB* is the single precision version of *DRANDBLUMBLUMSHUB*. The argument lists of both routines are identical except that any double precision arguments of *DRANDBLUMBLUMSHUB* are replaced in *SRANDBLUMBLUMSHUB* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDBLUMBLUMSHUB** (*N,STATE,X,INFO*) [SUBROUTINE]

**INTEGER** *N* [Input]

On input: number of variates required. The total number of bits generated is  $24N$ .

Constraint:  $N \geq 0$ .

**INTEGER** *STATE*(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDBLUMBLUMSHUB* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER** *X*(*N*) [Output]

On output: vector holding the bit stream. The least significant 24 bits of each of the  $X(i)$  contain the bit stream as generated by the Blum-Blum-Shub generator. The least significant bit of  $X(1)$  is the first bit generated, the second least significant bit of  $X(1)$  is the second bit generated etc.

**INTEGER** *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

**6.1.3 Basic NAG Generator**

The NAG basic generator is a linear congruential generator (LCG) and, like all LCGs, has the form:

$$x_i = a_1 x_{i-1} \bmod m_1,$$

$$u_i = \frac{x_i}{m_1},$$

where the  $u_i, i = 1, 2, \dots$  form the required sequence.

The NAG basic generator takes  $a_1 = 13^{13}$  and  $m_1 = 2^{59}$ , which gives a period of approximately  $2^{57}$ . This generator has been part of the NAG numerical library [9] since Mark 6 and as such has been widely used. It suffers from no known problems, other than those due to the lattice structure inherent in all LCGs, and, even though the period is relatively short compared to many of the newer generators, it is sufficiently large for many practical problems.

### 6.1.4 Wichmann-Hill Generator

The Wichmann-Hill [10] base generator uses a combination of four linear congruential generators (LCGs) and has the form:

$$\begin{aligned} w_i &= a_1 w_{i-1} \bmod m_1 \\ x_i &= a_2 x_{i-1} \bmod m_2 \\ y_i &= a_3 y_{i-1} \bmod m_3 \\ z_i &= a_4 z_{i-1} \bmod m_4 \\ u_i &= \left( \frac{w_i}{m_1} + \frac{x_i}{m_2} + \frac{y_i}{m_3} + \frac{z_i}{m_4} \right) \bmod 1, \end{aligned}$$

where the  $u_i, i = 1, 2, \dots$  form the required sequence. There are 273 sets of parameters,  $\{a_i, m_i : i = 1, 2, 3, 4\}$ , to choose from. These values have been selected so that the resulting generators are independent and have a period of approximately  $2^{80}$  [10].

### 6.1.5 Mersenne Twister

The Mersenne Twister [11] is a twisted generalized feedback shift register generator. The algorithm is as follows:

- Set some arbitrary initial values  $x_1, x_2, \dots, x_r$ , each consisting of  $w$  bits.
- Letting

$$A = \begin{pmatrix} 0 & I_{w-1} \\ a_w & a_{w-1} \cdots a_1 \end{pmatrix},$$

where  $I_{w-1}$  is the  $(w-1) \times (w-1)$  identity matrix and each of the  $a_i, i = 1$  to  $w$  take a value of either 0 or 1 (i.e. they can be represented as bits). Define

$$x_{i+r} = (x_{i+s} \oplus (x_i^{(w:(l+1))} | x_{i+1}^{(l:1)}) A),$$

where  $x_i^{(w:(l+1))} | x_{i+1}^{(l:1)}$  indicates the concatenation of the most significant (upper)  $w-l$  bits of  $x_i$  and the least significant (lower)  $l$  bits of  $x_{i+1}$ .

- Perform the following operations sequentially:

$$\begin{aligned} z &= x_{i+r} \oplus (x_{i+r} \gg t_1) \\ z &= z \oplus ((z \ll t_2) \text{ AND } m_1) \\ z &= z \oplus ((z \ll t_3) \text{ AND } m_2) \\ z &= z \oplus (z \gg t_4) \\ u_{i+r} &= z / (2^w - 1), \end{aligned}$$

where  $t_1, t_2, t_3$  and  $t_4$  are integers and  $m_1$  and  $m_2$  are bit-masks and “ $\gg t$ ” and “ $\ll t$ ” represent a  $t$  bit shift right and left respectively,  $\oplus$  is bit-wise exclusively or (xor) operation and “AND” is a bit-wise and operation.

The  $u_{i+r} : i = 1, 2, \dots$  then form a pseudo-random sequence, with  $u_i \in (0, 1)$ , for all  $i$ . This implementation of the Mersenne Twister uses the following values for the algorithmic



constants:

$$\begin{aligned}
 w &= 32 \\
 a &= 0x9908b0df \\
 l &= 31 \\
 r &= 624 \\
 s &= 397 \\
 t_1 &= 11 \\
 t_2 &= 7 \\
 t_3 &= 15 \\
 t_4 &= 18 \\
 m_1 &= 0x9d2c5680 \\
 m_2 &= 0xefc60000
 \end{aligned}$$

where the notation  $0xDD \dots$  indicates the bit pattern of the integer whose hexadecimal representation is  $DD \dots$ .

This algorithm has a period length of approximately  $2^{19,937} - 1$  and has been shown to be uniformly distributed in 623 dimensions.

### 6.1.6 L'Ecuyer's Combined Recursive Generator

The base generator referred to as L'Ecuyer's combined recursive generator is referred to as MRG32k3a in [12] and combines two multiple recursive generators:

$$\begin{aligned}
 x_i &= a_{11}x_{i-1} + a_{12}x_{i-2} + a_{13}x_{i-3} \bmod m_1 \\
 y_i &= a_{21}y_{i-1} + a_{22}y_{i-2} + a_{23}y_{i-3} \bmod m_2 \\
 z_i &= x_i - y_i \bmod m_1 \\
 u_i &= \frac{z_i}{m_1},
 \end{aligned}$$

where the  $u_i, i = 1, 2, \dots$  form the required sequence and  $a_{11} = 0, a_{12} = 1403580, a_{13} = 810728, m_1 = 2^{32} - 209, a_{21} = 527612, a_{22} = 0, a_{23} = 1370589$  and  $m_2 = 2^{32} - 22853$ .

Combining the two multiple recursive generators (MRG) results in sequences with better statistical properties in high dimensions and longer periods compared with those generated from a single MRG. The combined generator described above has a period length of approximately  $2^{191}$ .

### 6.1.7 Blum-Blum-Shub Generator

The Blum-Blum-Shub pseudo random number generator is cryptologically secure under the assumption that the quadratic residuosity problem is intractable [8]. The algorithm consists of the following:

- Generate two large and distinct primes,  $p$  and  $q$ , each congruent to 3 mod 4. Define  $m = pq$ .
- Select a seed  $s$  taking a value between 1 and  $m - 1$ , such that the greatest common divisor between  $s$  and  $m$  is 1.

- Let  $x_0 = s^2 \bmod m$ . For  $i = 1, 2, \dots$  generate:

$$x_i = x_{i-1}^2 \bmod m$$

$$z_i = v \text{ least significant bits of } x_i$$

where  $v \geq 1$ .

- The bit-sequence  $z_1, z_2, z_3, \dots$  is then the output sequence used.

### 6.1.8 User Supplied Generators

All of the distributional generators described in [Section 6.3 \[Distribution Generators\]](#), [page 86](#) require a base generator which returns a uniformly distributed value in the open interval  $(0, 1)$  and ACML includes several such generators (as detailed in [Section 6.1 \[Base Generators\]](#), [page 65](#)). However, for greater flexibility, the ACML routines allow the user to register their own base generator function. This user-supplied generator then becomes the base generator for all of the distribution generators.

A user supplied generator comes in the form of two routines, one to initialize the generator and one to generate a set of uniformly distributed values in the open interval  $(0, 1)$ . These two routines can be named anything, but are referred to as `UINI` for the initialization routine and `UGEN` for the generation routine in the following documentation.

In order to register a user supplied generator a call to `DRANDINITIALIZEUSER` must be made. Once registered the generator can be accessed and used in the same manner as the ACML supplied base generators. The specifications for `DRANDINITIALIZEUSER`, `UINI` and `UGEN` are given below. See the ACML example programs `drandinitializeuser_example.f` and `drandinitializeuser_c_example.c` ([Section 2.8 \[Examples\]](#), [page 15](#)) to understand how to use these routines in ACML.

**DRANDINITIALIZEUSER / SRANDINITIALIZEUSER**

Registers a user supplied base generator so that it can be used with the ACML distributional generators.

*(Note that SRANDINITIALIZEUSER is the single precision version of DRANDINITIALIZEUSER. The argument lists of both routines are identical except that any double precision arguments of DRANDINITIALIZEUSER are replaced in SRANDINITIALIZEUSER by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDINITIALIZEUSER** (*UINI,UGEN,GENID,SUBID,SEED,LSEED,STATE,LSTATE,INFO*) [SUBROUTINE]

**SUBROUTINE UINI** [Input]  
On input: routine that will be used to initialize the user supplied generator, *UGEN*.

**SUBROUTINE UGEN** [Input]  
On input: user supplied base generator.

**INTEGER GENID** [Input]  
On input: parameter is passed directly to *UINI*. Its function therefore depends on that routine.

**INTEGER SUBID** [Input]  
On input: parameter is passed directly to *UINI*. Its function therefore depends on that routine.

**INTEGER SEED(LSEED)** [Input]  
On input: parameter is passed directly to *UINI*. Its function therefore depends on that routine.

**INTEGER LSEED** [Input/Output]  
On input: length of the vector *SEED*. This parameter is passed directly to *UINI* and therefore its required value depends on that routine.  
On output: whether *LSEED* changes will depend on *UINI*.

**INTEGER STATE(LSTATE)** [Output]  
On output: the state vector required by all of the supplied distributional generators. The value of *STATE* returned by *UINI* has some housekeeping elements appended to the end before being returned by *DRANDINITIALIZEUSER*. See [Section 6.1.8 \[User Supplied Generators\]](#), [page 75](#) for details about the form of *STATE*.

**INTEGER LSTATE** [Input/Output]  
On input: length of the vector *STATE*. This parameter is passed directly to *UINI* and therefore its required value depends on that routine.

On output: whether *LSTATE* changes will depend on *UINI*. If  $LSTATE \leq 0$  then it is assumed that a request for the required length of *STATE* has been made. The value of *LSTATE* returned from *UINI* is therefore adjusted to allow

for housekeeping elements to be added to the end of the *STATE* vector. This results in the value of *LSTATE* returned by *DRANDINITIALIZEUSER* being 3 larger than that returned by *UINI*.

#### INTEGER INFO

[Output]

On output: *INFO* is an error indicator. *DRANDINITIALIZEUSER* will return a value of  $-6$  if the value of *LSTATE* is between 1 and 3. Otherwise *INFO* is passed directly back from *UINI*. It is recommended that the value of *INFO* returned by *UINI* is kept consistent with the rest of the ACML, that is if *INFO* =  $-i$  on exit, the *i*-th argument had an illegal value. If *INFO* = 1 on exit, then either, or both of *LSEED* and / or *LSTATE* have been set to the required length for vectors *SEED* and *STATE* respectively and the *STATE* vector has not have been initialized. If *INFO* = 0 then the state vector, *STATE*, has been successfully initialized.

Example:

```
C      Generate 100 values from the Uniform distribution using
C      a user supplied base generator
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,NSKIP,SEED(1),STATE(15)
      INTEGER X(N)
      DOUBLE PRECISION A,B

C      Set the seed
      SEED(1) = 1234

C      Set the distributional parameters
      A = 0.0D0
      B = 1.0D0

C      Initialize the base generator. Here ACMLRNGNBOGND is a user
C      supplied generator and ACMLRNGNB0INI its initializer
      CALL DRANDINITIALIZEUSER(ACMLRNGNB0INI,ACMLRNGNBOGND,1,0,SEED,
*      LSEED,STATE,LSTATE,INFO)

C      Generate N variates from the Univariate distribution
      CALL DRANDUNIFORM(N,A,B,STATE,X,LDX,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

## UINI

Specification for a user supplied initialization routine.

UINI (*GENID*,*SUBID*,*SEED*,*LSEED*,*STATE*,*LSTATE*,*INFO*) [SUBROUTINE]

INTEGER GENID [Input]

On input: the ID associated with the generator. It may be used for anything you like.

INTEGER SUBID [Input]

On input: the sub-ID associated with the generator. It may be used for anything you like.

INTEGER SEED(*LSEED*) [Input]

On input: an array containing the initial seed for your generator.

INTEGER LSEED [Input/Output]

On input: either the size of the *SEED* array, or a value  $< 1$ .

On output: if  $LSEED < 1$  on entry, *LSEED* must be set to the required size of the *SEED* array. This allows a caller of UINI to query the required size.

INTEGER STATE(*LSTATE*) [Output]

On output: if  $LSTATE < 1$  on entry, *STATE* should be unchanged.

Otherwise, *STATE* is a state vector holding internal details required by your generator. On exit from UINI, the array *STATE* must hold the following information:

$STATE(1) = ESTATE$ , where *ESTATE* is your minimum allowed size of array *STATE*.

$STATE(2) = MAGIC$ , where *MAGIC* is a magic number of your own choice. This can be used by your routine UGEN as a check that UINI has previously been called.

$STATE(3) = GENID$

$STATE(4) = SUBID$

$STATE(5) \dots STATE(ESTATE-1)$  = internal state values required by your generator routine UGEN; for example, the current value of your seed.

$STATE(ESTATE) = MAGIC$ , i.e. the same value as  $STATE(2)$ .

INTEGER LSTATE [Input/Output]

On input: either the size of the *STATE* array, or a value  $< 1$ .

On output: if  $LSTATE < 1$  on entry, *LSTATE* should be set to the required size of the *STATE* array, i.e. the value *ESTATE* as described above. This allows the caller of UINI to query the required size.

Constraint: either  $LSTATE < 1$  or  $LSTATE \geq ESTATE$ .

**INTEGER INFO** [Output]  
 On output: an error code, to be used in whatever way you wish; for example to flag an incorrect argument to UINI. If no error is encountered, UINI must set *INFO* to 0.

## UGEN

Specification for a user supplied base generator.

**UGEN** (*N,STATE,X,INFO*) [SUBROUTINE]

**INTEGER N** [Input]  
 On input: the number of random numbers to be generated.

**INTEGER STATE(\*)** [Input/Output]  
 On input: the internal state of your generator.

**DOUBLE PRECISION X(N)** [Output]  
 On output: the array of *N* uniform distributed random numbers, each in the half-open interval [0.0, 1.0) - i.e. 0.0 is a legitimate return value, but 1.0 is not.

**INTEGER INFO** [Output]  
 On output: a flag which you can use to signal an error in the call of UGEN - for example, if UGEN is called without being initialized by UINI.

## 6.2 Multiple Streams

It is often advantageous to be able to generate variates from multiple, independent, streams. For example when running a simulation in parallel on several processors. There are four ways of generating multiple streams using the routines available in the ACML:

- (a) Using different seeds
- (b) Using different sequences
- (c) Block-splitting or skipping ahead
- (d) Leap frogging

The four methods are detailed in the following sections. Of the four, (a) should be avoided in most cases, (b) is only really of any practical use when using the Wichmann-Hill generator, and is then still limited to 273 streams. Both block-splitting and leap-frogging work using the sequence from a single generator, both guarantee that the different sequences will not overlap and both can be scaled to an arbitrary number of streams. Leap-frogging requires no *a-priori* knowledge about the number of variates being generated, whereas block-splitting requires the user to know (approximately) the maximum number of variates required from each stream. Block-splitting requires no *a-priori* information on the number of streams required. In contrast leap-frogging requires the user to know the maximum number of streams required, prior to generating the first value.

It is known that, dependent on the number of streams required, leap-frogging can lead to sequences with poor statistical properties, especially when applied to linear congruential generators (see [Section 6.2.4 \[Leap Frogging\]](#), page 83 for a brief explanation). In addition, for more complicated generators like a L'Ecuyer's multiple recursive generator leap-frogging

can increase the time required to generate each variate compared to block-splitting. The additional time required by block-splitting occurs at the initialization stage, and not at the variate generation stage. Therefore in most instances block-splitting would be the preferred method for generating multiple sequences.

### 6.2.1 Using Different Seeds

A different sequence of variates can be generated from the same base generator by initializing the generator using a different set of seeds. Of the four methods for creating multiple streams described here, this is the least satisfactory. As mentioned in [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66, the statistical properties of the base generators are only guaranteed within sequences, not between sequences. For example, sequences generated from different starting points may overlap if the initial values are not far enough apart. The potential for overlapping sequences is reduced if the period of the generator being used is large. Although there is no guarantee of the independence of the sequences, due to its extremely large period, using the Mersenne Twister with random starting values is unlikely to lead to problems, especially if the number of sequences required is small. This is the only way in which multiple sequences can be generated with the ACML using the Mersenne Twister as the base generator.

If the statistical properties of different sequences must be provable then one of the other methods should be adopted.

### 6.2.2 Using Different Generators

Independent sequences of variates can be generated using different base generators for each sequence. For example, sequence 1 can be generated using the NAG basic generator, sequence 2 using the L'Ecuyer's Combined Recursive generator, sequence 3 using the Mersenne Twister. The Wichmann-Hill generator implemented in the ACML is in fact a series of 273 independent generators. The particular sub-generator being used can be selected using the *SUBID* variable (see [\[DRANDINITIALIZE\]](#), page 67 for details). Therefore, in total, 277 independent streams can be generated with each using an independent generator (273 Wichmann-Hill generators, and 4 additional base generators).

### 6.2.3 Skip Ahead

Independent sequences of variates can be generated from a single base generator through the use of block-splitting, or skipping-ahead. This method consists of splitting the sequence into  $k$  non-overlapping blocks, each of length  $n$ , where  $n$  is larger than the maximum number of variates required from any of the sequences. For example:

$$\frac{x_1, x_2, \dots, x_n}{\text{block 1}} \quad \frac{x_{n+1}, x_{n+2}, \dots, x_{2n}}{\text{block 2}} \quad \frac{x_{2n+1}, x_{2n+2}, \dots, x_{3n}}{\text{block 3}} \quad \text{etc}$$

where  $x_1, x_2, \dots$  is the sequence produced by the generator of interest. Each of the  $k$  blocks provide an independent sequence.

The block splitting algorithm therefore requires the sequence to be advanced a large number of places. Due to their form this can be done efficiently for linear congruential generators and multiple congruential generators. The ACML provides block-splitting for the

NAG Basic generator, the Wichmann-Hill generators and L'Ecuyer's Combined Recursive generator.



**DRANDSKIPAHEAD / SRANDSKIPAHEAD**

Advance a generator  $N$  places.

*(Note that SRANDSKIPAHEAD is the single precision version of DRANDSKIPAHEAD. The argument lists of both routines are identical except that any double precision arguments of DRANDSKIPAHEAD are replaced in SRANDSKIPAHEAD by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDSKIPAHEAD** ( $N, STATE, INFO$ )

[SUBROUTINE]

INTEGER  $N$

[Input]

On input: number of places to skip ahead.

Constraint:  $N \geq 0$ .

INTEGER  $STATE(*)$

[Input/Output]

The  $STATE$  vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDSKIPAHEAD  $STATE$  must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the  $STATE$  variable.

On input: the current state of the base generator.

On output: The  $STATE$  vector for a generator that has been advanced  $N$  places.

Constraint: The  $STATE$  vector must be for either the NAG basic, Wichmann-Hill or L'Ecuyer Combined Recursive base generators.

INTEGER  $INFO$

[Output]

On output:  $INFO$  is an error indicator. On successful exit,  $INFO$  contains 0.

If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```

C      Generate 3 * 100 values from the Uniform distribution
C      Multiple streams generated using the Skip Ahead method
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,NSKIP,SEED(1),STATE1(15),STATE2(15),STATE3(15)
      INTEGER X1(N),X2(N),X3(N)
      DOUBLE PRECISION A,B

C      Set the seed
      SEED(1) = 1234

C      Set the distributional parameters
      A = 0.0D0
      B = 1.0D0

C      Initialize the STATE1 vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE1,15,INFO)

C      Copy the STATE1 vector into other state vectors
      DO 20 I = 1,15
          STATE2(I) = STATE1(I)
          STATE3(I) = STATE1(I)
20    CONTINUE

C      Calculate how many places we want to skip, this
C      should be >> than the number of variates we
C      wish to generate from each stream
      NSKIP = N * N

C      Advance each stream, first does not need changing
      CALL DRANDSKIPAHEAD(NSKIP,STATE2,INFO)
      CALL DRANDSKIPAHEAD(2*NSKIP,STATE3,INFO)

C      Generate 3 sets of N variates from the Univariate distribution
      CALL DRANDUNIFORM(N,A,B,STATE1,X1,LDX,INFO)
      CALL DRANDUNIFORM(N,A,B,STATE2,X2,LDX,INFO)
      CALL DRANDUNIFORM(N,A,B,STATE3,X3,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
          WRITE(6,*) X1(I),X2(I),X3(I)
40    CONTINUE

```

### 6.2.4 Leap Frogging

Independent sequences of variates can be generated from a single base generator through the use of leap-frogging. This method involves splitting the sequence from a single generator

into  $k$  disjoint subsequences. For example:

$$\begin{aligned} \text{Subsequence 1 : } & x_1, x_{k+1}, x_{2k+1}, \dots \\ \text{Subsequence 2 : } & x_2, x_{k+2}, x_{2k+2}, \dots \\ & \vdots \\ \text{Subsequence } k : & x_k, x_{2k}, x_{3k}, \dots \end{aligned}$$

each subsequence is then provides an independent stream.

The leap-frog algorithm therefore requires the generation of every  $k$ th variate of a sequence. Due to their form this can be done efficiently for linear congruential generators and multiple congruential generators. The ACML provides leap-frogging for the NAG Basic generator, the Wichmann-Hill generators and L'Ecuyer's Combined Recursive generator.

As an illustrative example, a brief description of the algebra behind the implementation of the leap-frog algorithm (and block-splitting algorithm) for a linear congruential generator (LCG) will be given. A linear congruential generator has the form  $x_{i+1} = a_1 x_i \bmod m_1$ . The recursive nature of a LCG means that

$$\begin{aligned} x_{i+v} &= a_1 x_{i+v-1} \bmod m_1 \\ &= a_1 (a_1 x_{i+v-2} \bmod m_1) \bmod m_1 \\ &= a_1^2 x_{i+v-2} \bmod m_1 \\ &= a_1^v x_i \bmod m_1 \end{aligned}$$

The sequence can be quickly advanced  $v$  places by multiplying the current state ( $x_i$ ) by  $a_1^v \bmod m_1$ , hence allowing block-splitting. Leap-frogging is implemented by using  $a_1^k$ , where  $k$  is the number of streams required, in place of  $a_1$  in the standard LCG recursive formula. In a linear congruential generator the multiplier  $a_1$  is constructed so that the generator has good statistical properties in, for example, the spectral test. When using leap-frogging to construct multiple streams this multiplier is replaced with  $a_1^k$ , and there is no guarantee that this new multiplier will have suitable properties especially as the value of  $k$  depends on the number of streams required and so is likely to change depending on the application. This problem can be emphasised by the lattice structure of LCGs.

Note that, due to rounding, a sequence generated using leap-frogging and a sequence constructed by taking every  $k$ th value from a set of variates generated without leap-frogging may differ slightly. These differences should only affect the least significant digit.

**DRANDLEAPFROG / SRANDLEAPFROG**

Amend a generator so that it will generate every  $K$ th value.

*(Note that SRANDLEAPFROG is the single precision version of DRANDLEAPFROG. The argument lists of both routines are identical except that any double precision arguments of DRANDLEAPFROG are replaced in SRANDLEAPFROG by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDLEAPFROG (N,K,STATE,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: total number of streams being used.

Constraint:  $N > 0$ .

**INTEGER K** [Input]

On input: number of the current stream

Constraint:  $0 < K \leq N$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDLEAPFROG *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: The *STATE* vector for a generator that has been advanced  $K - 1$  places and will return every  $N$ th value.

Constraint: The *STATE* array must be for either the NAG basic, Wichmann-Hill or L'Ecuyer Combined Recursive base generators.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```

C      Generate 3 * 100 values from the Uniform distribution
C      Multiple streams generated using the Leap Frog method
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE1(15),STATE2(15),STATE3(15)
      INTEGER X1(N),X2(N),X3(N)
      DOUBLE PRECISION A,B

C      Set the seed
      SEED(1) = 1234

C      Set the distributional parameters
      A = 0.0D0
      B = 1.0D0

C      Initialize the STATE1 vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE1,15,INFO)

C      Copy the STATE1 vector into other state vectors
      DO 20 I = 1,15
          STATE2(I) = STATE1(I)
          STATE3(I) = STATE1(I)
20    CONTINUE

C      Update each stream so they generate every 3rd value
      CALL DRANDLEAPFROG(3,1,STATE1,INFO)
      CALL DRANDLEAPFROG(3,2,STATE2,INFO)
      CALL DRANDLEAPFROG(3,3,STATE3,INFO)

C      Generate 3 sets of N variates from the Univariate distribution
      CALL DRANDUNIFORM(N,A,B,STATE1,X1,LDX,INFO)
      CALL DRANDUNIFORM(N,A,B,STATE2,X2,LDX,INFO)
      CALL DRANDUNIFORM(N,A,B,STATE3,X3,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
          WRITE(6,*) X1(I),X2(I),X3(I)
40    CONTINUE

```

## 6.3 Distribution Generators

### 6.3.1 Continuous Univariate Distributions

#### DRANDBETA / SRANDBETA

Generates a vector of random variates from a beta distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{\Gamma(A+B)}{\Gamma(A)\Gamma(B)} X^{A-1} (1-X)^{B-1}$$

if  $0 \leq X \leq 1$  and  $A, B > 0.0$ , otherwise  $f(X) = 0$ .

*(Note that SRANDBETA is the single precision version of DRANDBETA. The argument lists of both routines are identical except that any double precision arguments of DRANDBETA are replaced in SRANDBETA by single precision arguments - type REAL in FORTRAN or type float in C).*

DRANDBETA (N,A,B,STATE,X,INFO) [SUBROUTINE]

INTEGER N [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

DOUBLE PRECISION A [Input]

On input: first parameter for the distribution.

Constraint:  $A > 0$ .

DOUBLE PRECISION B [Input]

On input: second parameter for the distribution.

Constraint:  $B > 0$ .

INTEGER STATE(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDBETA *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

DOUBLE PRECISION X(N) [Output]

On output: vector of variates from the specified distribution.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Beta distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Beta distribution
      CALL DRANDBETA(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDCAUCHY / SRANDCAUCHY**

Generates a vector of random variates from a Cauchy distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{1}{\pi B(1 + (\frac{X-A}{B})^2)}$$

(Note that *SRANDCAUCHY* is the single precision version of *DRANDCAUCHY*. The argument lists of both routines are identical except that any double precision arguments of *DRANDCAUCHY* are replaced in *SRANDCAUCHY* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDCAUCHY (N,A,B,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A** [Input]

On input: median of the distribution.

**DOUBLE PRECISION B** [Input]

On input: semi-quartile range of the distribution.

Constraint:  $B \geq 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDCAUCHY* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:



```
C      Generate 100 values from the Cauchy distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Cauchy distribution
      CALL DRANDCAUCHY(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDCHISQUARED / SRANDCHISQUARED**

Generates a vector of random variates from a  $\chi^2$  distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{X^{\frac{\nu}{2}-1} e^{-\frac{X}{2}}}{2^{\frac{\nu}{2}} (\frac{\nu}{2} - 1)!},$$

if  $X > 0$ , otherwise  $f(X) = 0$ . Here  $\nu$  is the degrees of freedom,  $DF$ .

*(Note that SRANDCHISQUARED is the single precision version of DRANDCHISQUARED. The argument lists of both routines are identical except that any double precision arguments of DRANDCHISQUARED are replaced in SRANDCHISQUARED by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDCHISQUARED (N,DF,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER DF** [Input]

On input: degrees of freedom of the distribution.

Constraint:  $DF > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDCHISQUARED** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Chi-squared distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER DF
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) DF

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Chi-squared distribution
      CALL DRANDCHISQUARED(N,DF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDEXPONENTIAL / SRANDEXPONENTIAL**

Generates a vector of random variates from an exponential distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{e^{-\frac{X}{A}}}{A}$$

if  $X > 0$ , otherwise  $f(X) = 0$ .

*(Note that SRANDEXPONENTIAL is the single precision version of DRANDEXPONENTIAL. The argument lists of both routines are identical except that any double precision arguments of DRANDEXPONENTIAL are replaced in SRANDEXPONENTIAL by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDEXPONENTIAL (N,A,STATE,X,INFO)**

[SUBROUTINE]

**INTEGER N**

[Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A**

[Input]

On input: exponential parameter.

Constraint:  $A \geq 0$ .

**INTEGER STATE(\*)**

[Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDEXPONENTIAL** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)**

[Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO**

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Exponential distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Exponential distribution
      CALL DRANDEXPONENTIAL(N,A,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDF / SRANDF**

Generates a vector of random variates from an F distribution, also called the Fisher's variance ratio distribution, with probability density function,  $f(X)$ , where:

$$f(X) = \frac{(\frac{\mu+\nu-2}{2})! X^{\frac{\mu}{2}-1} \mu^{\frac{\mu}{2}}}{(\frac{\mu}{2}-1)! (\frac{\nu}{2}-1)! (1 + \frac{\mu X}{\nu})^{\frac{\mu+\nu}{2}} \nu^{\frac{\nu}{2}}},$$

if  $X > 0$ , otherwise  $f(X) = 0$ . Here  $\mu$  is the first degrees of freedom, (*DF1*) and  $\nu$  is the second degrees of freedom, (*DF2*).

(Note that *SRANDF* is the single precision version of *DRANDF*. The argument lists of both routines are identical except that any double precision arguments of *DRANDF* are replaced in *SRANDF* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDF** (*N,DF1,DF2,STATE,X,INFO*) [SUBROUTINE]

**INTEGER** *N* [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER** *DF1* [Input]

On input: first degrees of freedom.

Constraint:  $DF1 \geq 0$ .

**INTEGER** *DF2* [Input]

On input: second degrees of freedom.

Constraint:  $DF2 \geq 0$ .

**INTEGER** *STATE*(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDF* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION** *X*(*N*) [Output]

On output: vector of variates from the specified distribution.

**INTEGER** *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the F distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER DF1,DF2
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) DF1,DF2

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the F distribution
      CALL DRANDF(N,DF1,DF2,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDGAMMA / SRANDGAMMA**

Generates a vector of random variates from a Gamma distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{X^{A-1} e^{-\frac{X}{B}}}{B^A \Gamma(A)},$$

if  $X \geq 0$  and  $A, B > 0.0$ , otherwise  $f(X) = 0$ .

*(Note that SRANDGAMMA is the single precision version of DRANDGAMMA. The argument lists of both routines are identical except that any double precision arguments of DRANDGAMMA are replaced in SRANDGAMMA by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDGAMMA (N,A,B,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A** [Input]

On input: first parameter of the distribution.

Constraint:  $A > 0$ .

**DOUBLE PRECISION B** [Input]

On input: second parameter of the distribution.

Constraint:  $B > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDGAMMA** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:



```
C      Generate 100 values from the Gamma distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Gamma distribution
      CALL DRANDGAMMA(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDGAUSSIAN / DRANDGAUSSIAN**

Generates a vector of random variates from a Gaussian distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{e^{-\frac{(X-\mu)^2}{2\sigma^2}}}{\sigma\sqrt{2\pi}}.$$

Here  $\mu$  is the mean, (*XMU*) and  $\sigma^2$  the variance, (*VAR*) of the distribution.

*(Note that SRANDGAUSSIAN is the single precision version of DRANDGAUSSIAN. The argument lists of both routines are identical except that any double precision arguments of DRANDGAUSSIAN are replaced in SRANDGAUSSIAN by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDGAUSSIAN (N, XMU, VAR, STATE, X, INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION XMU** [Input]

On input: mean of the distribution.

**DOUBLE PRECISION VAR** [Input]

On input: variance of the distribution.

Constraint:  $VAR \geq 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDGAUSSIAN** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Gaussian distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION XMU,VAR
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) XMU,VAR

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Gaussian distribution
      CALL DRANDGAUSSIAN(N,XMU,VAR,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDLOGISTIC / SRANDLOGISTIC**

Generates a vector of random variates from a logistic distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{e^{\frac{(X-A)}{B}}}{B(1 + e^{\frac{(X-A)}{B}})^2}.$$

*(Note that SRANDLOGISTIC is the single precision version of DRANDLOGISTIC. The argument lists of both routines are identical except that any double precision arguments of DRANDLOGISTIC are replaced in SRANDLOGISTIC by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDLOGISTIC (N,A,B,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A** [Input]

On input: mean of the distribution.

**DOUBLE PRECISION B** [Input]

On input: spread of the distribution.  $B = \sqrt{3}\sigma/\pi$  where  $\sigma$  is the standard deviation of the distribution.

Constraint:  $B > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDLOGISTIC** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Logistic distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Logistic distribution
      CALL DRANDLOGISTIC(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDLOGNORMAL / SRANDLOGNORMAL**

Generates a vector of random variates from a lognormal distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{e^{-\frac{(\log X - \mu)^2}{2\sigma^2}}}{X\sigma\sqrt{2\pi}},$$

if  $X > 0$ , otherwise  $f(X) = 0$ . Here  $\mu$  is the mean, ( $XMU$ ) and  $\sigma^2$  the variance, ( $VAR$ ) of the underlying Gaussian distribution.

*(Note that SRANDLOGNORMAL is the single precision version of DRANDLOGNORMAL. The argument lists of both routines are identical except that any double precision arguments of DRANDLOGNORMAL are replaced in SRANDLOGNORMAL by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDLOGNORMAL** ( $N, XMU, VAR, STATE, X, INFO$ ) [SUBROUTINE]

**INTEGER**  $N$  [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION**  $XMU$  [Input]

On input: mean of the underlying Gaussian distribution.

**DOUBLE PRECISION**  $VAR$  [Input]

On input: variance of the underlying Gaussian distribution.

Constraint:  $VAR \geq 0$ .

**INTEGER**  $STATE(*)$  [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDLOGNORMAL** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION**  $X(N)$  [Output]

On output: vector of variates from the specified distribution.

**INTEGER**  $INFO$  [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Lognormal distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION XMU,VAR
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) XMU,VAR

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Lognormal distribution
      CALL DRANDLOGNORMAL(N,XMU,VAR,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDSTUDENTST / SRANDSTUDENTST**

Generates a vector of random variates from a Students T distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{\frac{(\nu-1)!}{2}}{(\frac{\nu}{2})! \sqrt{\pi\nu} (1 + \frac{X^2}{\nu})^{\frac{(\nu+1)}{2}}}.$$

Here  $\nu$  is the degrees of freedom,  $DF$ .

*(Note that SRANDSTUDENTST is the single precision version of DRANDSTUDENTST. The argument lists of both routines are identical except that any double precision arguments of DRANDSTUDENTST are replaced in SRANDSTUDENTST by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDSTUDENTST (N,DF,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER DF** [Input]

On input: degrees of freedom.

Constraint:  $DF > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDSTUDENTST *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), [page 66](#) for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:



```
C      Generate 100 values from the Students T distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER DF
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) DF

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Students T distribution
      CALL DRANDSTUDENTST(N,DF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDTRIANGULAR / SRANDTRIANGULAR**

Generates a vector of random variates from a Triangular distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{2(X - X_{\text{MIN}})}{(X_{\text{MAX}} - X_{\text{MIN}})(X_{\text{MED}} - X_{\text{MIN}})},$$

if  $X_{\text{MIN}} < X \leq X_{\text{MED}}$ , else

$$f(X) = \frac{2(X_{\text{MAX}} - X)}{(X_{\text{MAX}} - X_{\text{MIN}})(X_{\text{MAX}} - X_{\text{MED}})},$$

if  $X_{\text{MED}} < X \leq X_{\text{MAX}}$ , otherwise  $f(X) = 0$ .

(Note that *SRANDTRIANGULAR* is the single precision version of *DRANDTRIANGULAR*. The argument lists of both routines are identical except that any double precision arguments of *DRANDTRIANGULAR* are replaced in *SRANDTRIANGULAR* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDTRIANGULAR** (*N,XMIN,XMED,XMAX,STATE,X,INFO*) [SUBROUTINE]

**INTEGER** *N* [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION** *XMIN* [Input]

On input: minimum value for the distribution.

**DOUBLE PRECISION** *XMED* [Input]

On input: median value for the distribution.

Constraint:  $X_{\text{MIN}} \leq X_{\text{MED}} \leq X_{\text{MAX}}$ .

**DOUBLE PRECISION** *XMAX* [Input]

On input: maximum value for the distribution.

Constraint:  $X_{\text{MAX}} \geq X_{\text{MIN}}$ .

**INTEGER** *STATE*(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDTRIANGULAR** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION** *X*(*N*) [Output]

On output: vector of variates from the specified distribution.

INTEGER INFO

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.  
If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```
C      Generate 100 values from the Triangular distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION XMIN,XMAX,XMED
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) XMIN,XMAX,XMED

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Triangular distribution
      CALL DRANDTRIANGULAR(N,XMIN,XMAX,XMED,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDUNIFORM / SRANDUNIFORM**

Generates a vector of random variates from a Uniform distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{1}{B - A}.$$

*(Note that SRANDUNIFORM is the single precision version of DRANDUNIFORM. The argument lists of both routines are identical except that any double precision arguments of DRANDUNIFORM are replaced in SRANDUNIFORM by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDUNIFORM (N,A,B,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A** [Input]

On input: minimum value for the distribution.

**DOUBLE PRECISION B** [Input]

On input: maximum value for the distribution.

Constraint:  $B \geq A$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDUNIFORM *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Uniform distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Uniform distribution
      CALL DRANDUNIFORM(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDVONMISES / SRANDVONMISES**

Generates a vector of random variates from a Von Mises distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{e^{\kappa \cos X}}{2\pi I_0(\kappa)}$$

where  $X$  is reduced modulo  $2\pi$  so that it lies between  $\pm\pi$ , and  $\kappa$  is the concentration parameter  $VK$ .

*(Note that SRANDVONMISES is the single precision version of DRANDVONMISES. The argument lists of both routines are identical except that any double precision arguments of DRANDVONMISES are replaced in SRANDVONMISES by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDVONMISES (N,VK,,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION VK** [Input]

On input: concentration parameter.

Constraint:  $VK > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDVONMISES** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Von Mises distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION VK
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) VK

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Von Mises distribution
      CALL DRANDVONMISES(N,VK,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDWEIBULL / SRANDWEIBULL**

Generates a vector of random variates from a Weibull distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{AX^{A-1}e^{-\frac{X^A}{B}}}{B},$$

if  $X > 0$ , otherwise  $f(X) = 0$ .

*(Note that SRANDWEIBULL is the single precision version of DRANDWEIBULL. The argument lists of both routines are identical except that any double precision arguments of DRANDWEIBULL are replaced in SRANDWEIBULL by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDWEIBULL (N,A,B,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION A** [Input]

On input: shape parameter for the distribution.

Constraint:  $A > 0$ .

**DOUBLE PRECISION B** [Input]

On input: scale parameter for the distribution.

Constraint:  $B > 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDWEIBULL *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:



```
C      Generate 100 values from the Weibull distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION A,B
      DOUBLE PRECISION X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Weibull distribution
      CALL DRANDWEIBULL(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

### 6.3.2 Discrete Univariate Distributions

#### DRANDBINOMIAL / SRANDBINOMIAL

Generates a vector of random variates from a Binomial distribution with probability,  $f(X)$ , defined by:

$$f(X) = \frac{M!P^X(1-P)^{(M-X)}}{X!(M-X)!}, X = 0, 1, \dots, M$$

*(Note that SRANDBINOMIAL is the single precision version of DRANDBINOMIAL. The argument lists of both routines are identical except that any double precision arguments of DRANDBINOMIAL are replaced in SRANDBINOMIAL by single precision arguments - type REAL in FORTRAN or type float in C).*

DRANDBINOMIAL (N,M,P,STATE,X,INFO) [SUBROUTINE]

INTEGER N [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

INTEGER M [Input]

On input: number of trials.

Constraint:  $M \geq 0$ .

DOUBLE PRECISION P [Input]

On input: probability of success.

Constraint:  $0 \leq P < 1$ .

INTEGER STATE(\*) [Input/Output]

The STATE vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDBINOMIAL STATE must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the STATE variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

INTEGER X(N) [Output]

On output: vector of variates from the specified distribution.

INTEGER INFO [Output]

On output: INFO is an error indicator. On successful exit, INFO contains 0. If  $INFO = -i$  on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Binomial distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER M
      DOUBLE PRECISION P
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Binomial distribution
      CALL DRANDBINOMIAL(N,M,P,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDGEOMETRIC / SRANDGEOMETRIC**

Generates a vector of random variates from a Geometric distribution with probability,  $f(X)$ , defined by:

$$f(X) = P(1 - P)^{(X-1)}, X = 1, 2, \dots$$

*(Note that SRANDGEOMETRIC is the single precision version of DRANDGEOMETRIC. The argument lists of both routines are identical except that any double precision arguments of DRANDGEOMETRIC are replaced in SRANDGEOMETRIC by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDGEOMETRIC (N,P,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION P** [Input]

On input: distribution parameter.

Constraint:  $0 \leq P < 1$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDGEOMETRIC** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), [page 66](#) for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If  $INFO = -i$  on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Geometric distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION P
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Geometric distribution
      CALL DRANDGEOMETRIC(N,P,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDHYPERGEOMETRIC / SRANDHYPERGEOMETRIC**

Generates a vector of random variates from a Hypergeometric distribution with probability,  $f(X)$ , defined by:

$$f(X) = \frac{s!m!(p-s)!(p-m)!}{X!(s-X)!(m-X)!(p-m-s+X)!p!},$$

if  $X = \max(0, m + s - p), \dots, \min(l, m)$ , otherwise  $f(X) = 0$ . Here  $p$  is the size of the population, ( $NP$ ),  $s$  is the size of the sample taken from the population, ( $NS$ ) and  $m$  is the number of labeled, or specified, items in the population, ( $M$ ).

*(Note that SRANDHYPERGEOMETRIC is the single precision version of DRANDHYPERGEOMETRIC. The argument lists of both routines are identical except that any double precision arguments of DRANDHYPERGEOMETRIC are replaced in SRANDHYPERGEOMETRIC by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDHYPERGEOMETRIC** ( $N, NP, NS, M, STATE, X, INFO$ ) [SUBROUTINE]

**INTEGER**  $N$  [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER**  $NP$  [Input]

On input: size of population.

Constraint:  $NP \geq 0$ .

**INTEGER**  $NS$  [Input]

On input: size of sample being taken from population.

Constraint:  $0 \leq NS \leq NP$ .

**INTEGER**  $M$  [Input]

On input: number of specified items in the population.

Constraint:  $0 \leq M \leq NP$ .

**INTEGER**  $STATE(*)$  [Input/Output]

The  $STATE$  vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDHYPERGEOMETRIC**  $STATE$  must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the  $STATE$  variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

INTEGER X(N) [Output]

On output: vector of variates from the specified distribution.

INTEGER INFO [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Hypergeometric distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER NP,NS,M
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) NP,NS,M

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Hypergeometric distribution
      CALL DRANDHYPERGEOMETRIC(N,NP,NS,M,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDNEGATIVEBINOMIAL / SRANDNEGATIVEBINOMIAL**

Generates a vector of random variates from a Negative Binomial distribution with probability  $f(X)$  defined by:

$$f(X) = \frac{(M + X - 1)! P^X (1 - P)^M}{X! (M - 1)!}, X = 0, 1, \dots$$

*(Note that SRANDNEGATIVEBINOMIAL is the single precision version of DRANDNEGATIVEBINOMIAL. The argument lists of both routines are identical except that any double precision arguments of DRANDNEGATIVEBINOMIAL are replaced in SRANDNEGATIVEBINOMIAL by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDNEGATIVEBINOMIAL (N,M,P,STATE,X,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER M** [Input]

On input: number of failures.

Constraint:  $M \geq 0$ .

**DOUBLE PRECISION P** [Input]

On input: probability of success.

Constraint:  $0 \leq P < 1$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDNEGATIVEBINOMIAL *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.



Example:

```
C      Generate 100 values from the Negative Binomial distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER M
      DOUBLE PRECISION P
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Negative Binomial distribution
      CALL DRANDNEGATIVEBINOMIAL(N,M,P,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDPOISSON / SRANDPOISSON**

Generates a vector of random variates from a Poisson distribution with probability  $f(X)$  defined by:

$$f(X) = \frac{\lambda^X e^{-\lambda}}{X!}, X = 0, 1, \dots,$$

where  $\lambda$  is the mean of the distribution, *LAMBDA*.

*(Note that SRANDPOISSON is the single precision version of DRANDPOISSON. The argument lists of both routines are identical except that any double precision arguments of DRANDPOISSON are replaced in SRANDPOISSON by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDPOISSON** (*N,LAMBDA,STATE,X,INFO*) [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER M** [Input]

On input: number of failures.

Constraint:  $M \geq 0$ .

**DOUBLE PRECISION LAMBDA** [Input]

On input: mean of the distribution.

Constraint:  $LAMBDA \geq 0$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling **DRANDPOISSON** *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Poisson distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION LAMBDA
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) LAMBDA

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Poisson distribution
      CALL DRANDPOISSON(N,LAMBDA,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDDISCRETEUNIFORM / SRANDDISCRETEUNIFORM**

Generates a vector of random variates from a Uniform distribution with probability  $f(X)$  defined by:

$$f(X) = \frac{1}{(B - A)}, X = A, A + 1, \dots, B$$

(Note that *SRANDDISCRETEUNIFORM* is the single precision version of *DRANDDISCRETEUNIFORM*. The argument lists of both routines are identical except that any double precision arguments of *DRANDDISCRETEUNIFORM* are replaced in *SRANDDISCRETEUNIFORM* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDDISCRETEUNIFORM** (*N,A,B,STATE,X,INFO*) [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER A** [Input]

On input: minimum for the distribution.

**INTEGER B** [Input]

On input: maximum for the distribution.

Constraint:  $B \geq A$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDDISCRETEUNIFORM* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Uniform distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER A,B
      INTEGER X(N)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) A,B

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Uniform distribution
      CALL DRANDDISCRETEUNIFORM(N,A,B,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDGENERALDISCRETE / SRANDGENERALDISCRETE**

Takes a reference vector initialized via one of DRANDBINOMIALREFERENCE, DRANDGEOMETRICREFERENCE, DRANDHYPERGEOMETRICREFERENCE, DRANDNEGATIVEBINOMIALREFERENCE, DRANDPOISSONREFERENCE and generates a vector of random variates from it.

*(Note that SRANDGENERALDISCRETE is the single precision version of DRANDGENERALDISCRETE. The argument lists of both routines are identical except that any double precision arguments of DRANDGENERALDISCRETE are replaced in SRANDGENERALDISCRETE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDGENERALDISCRETE** (*N,REF,STATE,X,INFO*) [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION REF(\*)** [Input]

On input: reference vector generated by one of the following: DRANDBINOMIALREFERENCE, DRANDGEOMETRICREFERENCE, DRANDHYPERGEOMETRICREFERENCE, DRANDNEGATIVEBINOMIALREFERENCE, DRANDPOISSONREFERENCE.

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDGENERALDISCRETE *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**INTEGER X(N)** [Output]

On output: vector of variates from the specified distribution.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Binomial distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER M
      DOUBLE PRECISION P
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDBINOMIALREFERENCE(M,P,REF,LREF,INFO)

C      Generate N variates from the Binomial distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDBINOMIALREFERENCE / SRANDBINOMIALREFERENCE**

Initializes a reference vector for use with DRANDGENERALDISCRETE. Reference vector is for a Binomial distribution with probability,  $f(X)$ , defined by:

$$f(X) = \frac{M!P^X(1-P)^{(M-X)}}{X!(M-X)!}, X = 0, 1, \dots, M$$

*(Note that SRANDBINOMIALREFERENCE is the single precision version of DRANDBINOMIALREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDBINOMIALREFERENCE are replaced in SRANDBINOMIALREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDBINOMIALREFERENCE (N,M,P,REF,LREF,INFO)** [SUBROUTINE]

**INTEGER M** [Input]

On input: number of trials.

Constraint:  $M \geq 0$ .

**DOUBLE PRECISION P** [Input]

On input: probability of success.

Constraint:  $0 \leq P < 1$ .

**DOUBLE PRECISION REF(LREF)** [Output]

On output: if *INFO* returns with a value of 0 then *REF* contains reference information required to generate values from a Binomial distribution using DRANDGENERALDISCRETE.

**INTEGER LREF** [Input/Output]

On input: either the length of the reference vector *REF*, or  $-1$ .

On output: if *LREF* =  $-1$  on input, then *LREF* is set to the recommended length of the reference vector and the routine returns. Otherwise *LREF* is left unchanged.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. If *INFO* =  $-i$  on exit, the *i*-th argument had an illegal value. If *INFO* = 1 on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If *INFO* = 0 then the reference vector, *REF*, has been successfully initialized.

Example:



```
C      Generate 100 values from the Binomial distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER M
      DOUBLE PRECISION P
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDBINOMIALREFERENCE(M,P,REF,LREF,INFO)

C      Generate N variates from the Binomial distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDGEOMETRICREFERENCE / SRANDGEOMETRICREFERENCE**

Initializes a reference vector for use with DRANDGENERALDISCRETE. Reference vector is for a Geometric distribution with probability,  $f(X)$ , defined by:

$$f(X) = P(1 - P)^{(X-1)}, X = 1, 2, \dots$$

*(Note that SRANDGEOMETRICREFERENCE is the single precision version of DRANDGEOMETRICREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDGEOMETRICREFERENCE are replaced in SRANDGEOMETRICREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDGEOMETRICREFERENCE (N,P,REF,LREF,INFO)**

[SUBROUTINE]

**DOUBLE PRECISION P**

[Input]

On input: distribution parameter.

Constraint:  $0 \leq P < 1$ .

**DOUBLE PRECISION REF(LREF)**

[Output]

On output: if *INFO* returns with a value of 0 then *REF* contains reference information required to generate values from a Geometric distribution using DRANDGENERALDISCRETE.

**INTEGER LREF**

[Input/Output]

On input: either the length of the reference vector *REF*, or  $-1$ .

On output: if *LREF* =  $-1$  on input, then *LREF* is set to the recommended length of the reference vector and the routine returns. Otherwise *LREF* is left unchanged.

**INTEGER INFO**

[Output]

On output: *INFO* is an error indicator. If *INFO* =  $-i$  on exit, the *i*-th argument had an illegal value. If *INFO* = 1 on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If *INFO* = 0 then the reference vector, *REF*, has been successfully initialized.

Example:

```
C      Generate 100 values from the Geometric distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION P
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDGEOMETRICREFERENCE(P,REF,LREF,INFO)

C      Generate N variates from the Geometric distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

# DRANDHYPERGEOMETRICREFERENCE / SRANDHYPERGEOMETRICREFERENCE

Initializes a reference vector for use with DRANDGENERALDISCRETE. Reference vector is for a Hypergeometric distribution with probability,  $f(X)$ , defined by:

$$f(X) = \frac{s!m!(p-s)!(p-m)!}{X!(s-X)!(m-X)!(p-m-s+X)!p!},$$

if  $X = \max(0, m + s - p), \dots, \min(l, m)$ , otherwise  $f(X) = 0$ . Here  $p$  is the size of the population,  $(NP)$ ,  $s$  is the size of the sample taken from the population,  $(NS)$  and  $m$  is the number of labeled, or specified, items in the population,  $(M)$ .

*(Note that SRANDHYPERGEOMETRICREFERENCE is the single precision version of DRANDHYPERGEOMETRICREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDHYPERGEOMETRICREFERENCE are replaced in SRANDHYPERGEOMETRICREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

DRANDHYPERGEOMETRICREFERENCE (N,NP,NS,M,REF,LREF,INFO) [SUBROUTINE]

INTEGER NP [Input]

On input: size of population.

Constraint:  $NP \geq 0$ .

INTEGER NS [Input]

On input: size of sample being taken from population.

Constraint:  $0 \leq NS \leq NP$ .

INTEGER M [Input]

On input: number of specified items in the population.

Constraint:  $0 \leq M \leq NP$ .

DOUBLE PRECISION REF(LREF) [Output]

On output: if INFO returns with a value of 0 then REF contains reference information required to generate values from a Hypergeometric distribution using DRANDGENERALDISCRETE.

INTEGER LREF [Input/Output]

On input: either the length of the reference vector REF, or -1.

On output: if LREF = -1 on input, then LREF is set to the recommended length of the reference vector and the routine returns. Otherwise LREF is left unchanged.

INTEGER INFO [Output]

On output: INFO is an error indicator. If INFO = -i on exit, the i-th argument had an illegal value. If INFO = 1 on exit, then LREF has been set to the recommended length for the reference vector REF. If INFO = 0 then the reference vector, REF, has been successfully initialized.

Example:

```
C      Generate 100 values from the Hypergeometric distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER NP, NS,M
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) NP, NS,M

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDHYPERGEOMETRICREFERENCE(NP, NS,M,REF,LREF,INFO)

C      Generate N variates from the Hypergeometric distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDNEGATIVEBINOMIALREFERENCE / SRANDNEGATIVEBINOMIALREFERENCE**

Initializes a reference vector for use with DRANDGENERALDISCRETE. Reference vector is for a Negative Binomial distribution with probability  $f(X)$  defined by:

$$f(X) = \frac{(M + X - 1)! P^X (1 - P)^M}{X! (M - 1)!}, X = 0, 1, \dots$$

*(Note that SRANDNEGATIVEBINOMIALREFERENCE is the single precision version of DRANDNEGATIVEBINOMIALREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDNEGATIVEBINOMIALREFERENCE are replaced in SRANDNEGATIVEBINOMIALREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDNEGATIVEBINOMIALREFERENCE (N,M,P,REF,LREF,INFO)** [SUBROUTINE]

**INTEGER M** [Input]

On input: number of failures.

Constraint:  $M \geq 0$ .

**DOUBLE PRECISION P** [Input]

On input: probability of success.

Constraint:  $0 \leq P < 1$ .

**DOUBLE PRECISION REF(LREF)** [Output]

On output: if *INFO* returns with a value of 0 then *REF* contains reference information required to generate values from a Negative Binomial distribution using DRANDGENERALDISCRETE.

**INTEGER LREF** [Input/Output]

On input: either the length of the reference vector *REF*, or  $-1$ .

On output: if  $LREF = -1$  on input, then *LREF* is set to the recommended length of the reference vector and the routine returns. Otherwise *LREF* is left unchanged.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value. If  $INFO = 1$  on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If  $INFO = 0$  then the reference vector, *REF*, has been successfully initialized.

Example:

```
C      Generate 100 values from the Negative Binomial distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      INTEGER M
      DOUBLE PRECISION P
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,P

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDNEGATIVEBINOMIALREFERENCE(M,P,REF,LREF,INFO)

C      Generate N variates from the Negative Binomial distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

**DRANDPOISSONREFERENCE / SRANDPOISSONREFERENCE**

Initializes a reference vector for use with DRANDGENERALDISCRETE. Reference vector is for a Poisson distribution with probability  $f(X)$  defined by:

$$f(X) = \frac{\lambda^X e^{-\lambda}}{X!}, X = 0, 1, \dots,$$

where  $\lambda$  is the mean of the distribution, *LAMBDA*.

*(Note that SRANDPOISSONREFERENCE is the single precision version of DRANDPOISSONREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDPOISSONREFERENCE are replaced in SRANDPOISSONREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDPOISSONREFERENCE (N,LAMBDA,REF,LREF,INFO)** [SUBROUTINE]

**INTEGER M** [Input]

On input: number of failures.

Constraint:  $M \geq 0$ .

**DOUBLE PRECISION LAMBDA** [Input]

On input: mean of the distribution.

Constraint:  $LAMBDA \geq 0$ .

**DOUBLE PRECISION REF(LREF)** [Output]

On output: if *INFO* returns with a value of 0 then *REF* contains reference information required to generate values from a Poisson distribution using DRANDGENERALDISCRETE.

**INTEGER LREF** [Input/Output]

On input: either the length of the reference vector *REF*, or  $-1$ .

On output: if  $LREF = -1$  on input, then *LREF* is set to the recommended length of the reference vector and the routine returns. Otherwise *LREF* is left unchanged.

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. If  $INFO = -i$  on exit, the *i*-th argument had an illegal value. If  $INFO = 1$  on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If  $INFO = 0$  then the reference vector, *REF*, has been successfully initialized.

Example:



```
C      Generate 100 values from the Poisson distribution
      INTEGER N
      PARAMETER (N=100)
      INTEGER I,INFO,SEED(1),STATE(15)
      DOUBLE PRECISION LAMBDA
      INTEGER X(N)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) LAMBDA

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDPOISSONREFERENCE(LAMBDA,REF,LREF,INFO)

C      Generate N variates from the Poisson distribution
      CALL DRANDGENERALDISCRETE(N,REF,STATE,X,INFO)

C      Print the results
      WRITE(6,*) (X(I),I=1,N)
```

### 6.3.3 Continuous Multivariate Distributions

#### DRANDMULTINORMAL / SRANDMULTINORMAL

Generates an array of random variates from a Multivariate Normal distribution with probability density function,  $f(X)$ , where:

$$f(X) = \sqrt{\frac{|C^{-1}|}{(2\pi)^M}} e^{-(X-\mu)^T C^{-1} (X-\mu)},$$

where  $\mu$  is the vector of means,  $XMU$ .

(Note that *SRANDMULTINORMAL* is the single precision version of *DRANDMULTINORMAL*. The argument lists of both routines are identical except that any double precision arguments of *DRANDMULTINORMAL* are replaced in *SRANDMULTINORMAL* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

DRANDMULTINORMAL (N,M,XMU,C,LDC,STATE,X,LDX,INFO) [SUBROUTINE]

INTEGER N [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

INTEGER M [Input]

On input: number of dimensions for the distribution.

Constraint:  $M \geq 1$ .

DOUBLE PRECISION XMU(M) [Input]

On input: vector of means for the distribution.

DOUBLE PRECISION C(LDC,M) [Input]

On input: variance / covariance matrix for the distribution.

INTEGER LDC [Input]

On input: leading dimension of  $C$  in the calling routine.

Constraint:  $LDC \geq N$ .

INTEGER STATE(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDMULTINORMAL* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

DOUBLE PRECISION X(LDX,M) [Output]

On output: matrix of variates from the specified distribution.

INTEGER LDX

[Input]

On input: leading dimension of  $X$  in the calling routine.

Constraint:  $LDX \geq M$ .

INTEGER INFO

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.

If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```

C      Generate 100 values from the Multivariate Normal distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
        READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Multivariate Normal distribution
      CALL DRANDMULTINORMAL(N,M,XMU,C,LDC,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
        WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE

```

**DRANDMULTISTUDENTST / SRANDMULTISTUDENTST**

Generates an array of random variates from a Multivariate Students T distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{\Gamma\left(\frac{\nu+M}{2}\right)}{(\pi\nu)^{\frac{M}{2}} \Gamma\left(\frac{\nu}{2}\right) |C|^{\frac{1}{2}}} \left(1 + \frac{(X - \mu)^T C^{-1} (X - \mu)}{\nu}\right)^{-\frac{(\nu+M)}{2}},$$

where  $\mu$  is the vector of means,  $XMU$  and  $\nu$  is the degrees of freedom,  $DF$ .

(Note that *SRANDMULTISTUDENTST* is the single precision version of *DRANDMULTISTUDENTST*. The argument lists of both routines are identical except that any double precision arguments of *DRANDMULTISTUDENTST* are replaced in *SRANDMULTISTUDENTST* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

**DRANDMULTISTUDENTST** (*N,M,DF,XMU,C,LDC,STATE,X,LDX,INFO*) [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER M** [Input]

On input: number of dimensions for the distribution.

Constraint:  $M \geq 1$ .

**INTEGER DF** [Input]

On input: degrees of freedom.

Constraint:  $DF > 2$ .

**DOUBLE PRECISION XMU(M)** [Input]

On input: vector of means for the distribution.

**DOUBLE PRECISION C(LDC,M)** [Input]

On input: matrix defining the variance / covariance for the distribution. The variance / covariance matrix is given by  $\frac{\nu}{\nu-2}C$ , where  $\nu$  are the degrees of freedom,  $DF$ .

**INTEGER LDC** [Input]

On input: leading dimension of  $C$  in the calling routine.

Constraint:  $LDC \geq N$ .

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDMULTISTUDENTST* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization

of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

DOUBLE PRECISION *X*(*LDX*,*M*)

[Output]

On output: matrix of variates from the specified distribution.

INTEGER *LDX*

[Input]

On input: leading dimension of *X* in the calling routine.

Constraint:  $LDX \geq M$ .

INTEGER *INFO*

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.  
If *INFO* = -*i* on exit, the *i*-th argument had an illegal value.

Example:

```
C      Generate 100 values from the Multivariate Students T distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M,DF
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,DF
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
         READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Generate N variates from the Multivariate Students T distribution
      CALL DRANDMULTISTUDENTST(N,M,DF,XMU,C,LDC,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
         WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE
```

**DRANDMULTINORMALR / SRANDMULTINORMALR**

Generates an array of random variates from a Multivariate Normal distribution using a reference vector initialized by DRANDMULTINORMALREFERENCE.

*(Note that SRANDMULTINORMALR is the single precision version of DRANDMULTINORMALR. The argument lists of both routines are identical except that any double precision arguments of DRANDMULTINORMALR are replaced in SRANDMULTINORMALR by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDMULTINORMALR** (*N,REF,STATE,X,LDX,INFO*) [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION REF(\*)** [Input]

On input: a reference vector generated by DRANDMULTINORMALREFERENCE.

**INTEGER STATE(\*)** [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDMULTINORMALR *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION X(LDX,M)** [Output]

On output: matrix of variates from the specified distribution.

**INTEGER LDX** [Input]

On input: leading dimension of *X* in the calling routine.

Constraint:  $LDX \geq M$ .

**INTEGER INFO** [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

C      Generate 100 values from the Multivariate Normal distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
        READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDMULTINORMALREFERENCE(M,XMU,C,LDC,REF,LREF,INFO)

C      Generate N variates from the Multivariate Normal distribution
      CALL DRANDMULTINORMALR(N,REF,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
        WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE

```



**DRANDMULTISTUDENTSTR / SRANDMULTISTUDENTSTR**

Generates an array of random variates from a Multivariate Students T distribution using a reference vector initialized by DRANDMULTISTUDENTSTREFERENCE.

(Note that SRANDMULTISTUDENTSTR is the single precision version of DRANDMULTISTUDENTSTR. The argument lists of both routines are identical except that any double precision arguments of DRANDMULTISTUDENTSTR are replaced in SRANDMULTISTUDENTSTR by single precision arguments - type REAL in FORTRAN or type float in C).

**DRANDMULTISTUDENTSTR** (*N,REF,STATE,X,LDX,INFO*) [SUBROUTINE]

**INTEGER** *N* [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**DOUBLE PRECISION** *REF*(\*) [Input]

On input: a reference vector generated by DRANDMULTISTUDENTSTREFERENCE.

**INTEGER** *STATE*(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling DRANDMULTISTUDENTSTR *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

**DOUBLE PRECISION** *X*(*LDX*,*M*) [Output]

On output: matrix of variates from the specified distribution.

**INTEGER** *LDX* [Input]

On input: leading dimension of *X* in the calling routine.

Constraint:  $LDX \geq M$ .

**INTEGER** *INFO* [Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0. If *INFO* = -i on exit, the i-th argument had an illegal value.

Example:

```

C      Generate 100 values from the Multivariate Students T distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M,DF
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,DF
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
        READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDMULTISTUDENTSTREFERENCE(M,DF,XMU,C,LDC,REF,LREF,INFO)

C      Generate N variates from the Multivariate Students T distribution
      CALL DRANDMULTISTUDENTSTR(N,REF,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
        WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE

```

**DRANDMULTINORMALREFERENCE / SRANDMULTINORMALREFERENCE**

Initializes a reference vector for use with DRANDMULTINORMALR. Reference vector is for a Multivariate Normal distribution with probability density function,  $f(X)$ , where:

$$f(X) = \sqrt{\frac{|C^{-1}|}{(2\pi)^M}} e^{-(X-\mu)^T C^{-1} (X-\mu)},$$

where  $\mu$  is the vector of means,  $XMU$ .

*(Note that SRANDMULTINORMALREFERENCE is the single precision version of DRANDMULTINORMALREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDMULTINORMALREFERENCE are replaced in SRANDMULTINORMALREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDMULTINORMALREFERENCE (M,XMU,C,LDC,REF,LREF,INFO)** [SUBROUTINE]

**INTEGER N** [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

**INTEGER M** [Input]

On input: number of dimensions for the distribution.

Constraint:  $M \geq 1$ .

**DOUBLE PRECISION XMU(M)** [Input]

On input: vector of means for the distribution.

**DOUBLE PRECISION C(LDC,M)** [Input]

On input: variance / covariance matrix for the distribution.

**INTEGER LDC** [Input]

On input: leading dimension of  $C$  in the calling routine.

Constraint:  $LDC \geq N$ .

**DOUBLE PRECISION REF(LREF)** [Output]

On output: if  $INFO$  returns with a value of 0 then  $REF$  contains reference information required to generate values from a Multivariate Normal distribution using DRANDMULTINORMALR.

**INTEGER LREF** [Input/Output]

On input: either the length of the reference vector  $REF$ , or  $-1$ .

On output: if  $LREF = -1$  on input, then  $LREF$  is set to the recommended length of the reference vector and the routine returns. Otherwise  $LREF$  is left unchanged.

**INTEGER INFO**

[Output]

On output: *INFO* is an error indicator. If *INFO* = -i on exit, the i-th argument had an illegal value. If *INFO* = 1 on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If *INFO* = 0 then the reference vector, *REF*, has been successfully initialized.

Example:

```

C      Generate 100 values from the Multivariate Normal distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
        READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDMULTINORMALREFERENCE(M,XMU,C,LDC,REF,LREF,INFO)

C      Generate N variates from the Multivariate Normal distribution
      CALL DRANDMULTINORMALR(N,REF,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
        WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE

```

**DRANDMULTISTUDENTSTREFERENCE / SRANDMULTISTUDENTSTREFERENCE**

Initializes a reference vector for use with DRANDMULTISTUDENTSTR. Reference vector is for a Multivariate Students T distribution with probability density function,  $f(X)$ , where:

$$f(X) = \frac{\Gamma\left(\frac{(\nu+M)}{2}\right)}{(\pi\nu)^{\frac{M}{2}} \Gamma\left(\frac{\nu}{2}\right) |C|^{\frac{1}{2}}} \left(1 + \frac{(X - \mu)^T C^{-1} (X - \mu)}{\nu}\right)^{-\frac{(\nu+M)}{2}},$$

where  $\mu$  is the vector of means,  $XMU$  and  $\nu$  is the degrees of freedom,  $DF$ .

*(Note that SRANDMULTISTUDENTSTREFERENCE is the single precision version of DRANDMULTISTUDENTSTREFERENCE. The argument lists of both routines are identical except that any double precision arguments of DRANDMULTISTUDENTSTREFERENCE are replaced in SRANDMULTISTUDENTSTREFERENCE by single precision arguments - type REAL in FORTRAN or type float in C).*

**DRANDMULTISTUDENTSTREFERENCE** [SUBROUTINE]  
( $M, DF, XMU, C, LDC, REF, LREF, INFO$ )

**INTEGER M** [Input]  
On input: number of dimensions for the distribution.

Constraint:  $M \geq 1$ .

**INTEGER DF** [Input]  
On input: degrees of freedom.

Constraint:  $DF > 2$ .

**DOUBLE PRECISION XMU(M)** [Input]  
On input: vector of means for the distribution.

**DOUBLE PRECISION C(LDC, M)** [Input]  
On input: matrix defining the variance / covariance for the distribution. The variance / covariance matrix is given by  $\frac{\nu}{\nu-2}C$ , where  $\nu$  are the degrees of freedom,  $DF$ .

**INTEGER LDC** [Input]  
On input: leading dimension of  $C$  in the calling routine.

Constraint:  $LDC \geq N$ .

**DOUBLE PRECISION REF(LREF)** [Output]  
On output: if  $INFO$  returns with a value of 0 then  $REF$  contains reference information required to generate values from a Multivariate Students T distribution using DRANDMULTISTUDENTSTR.

**INTEGER LREF** [Input/Output]  
On input: either the length of the reference vector  $REF$ , or  $-1$ .

On output: if  $LREF = -1$  on input, then  $LREF$  is set to the recommended length of the reference vector and the routine returns. Otherwise  $LREF$  is left unchanged.

**INTEGER INFO**

[Output]

On output: *INFO* is an error indicator. If *INFO* = -i on exit, the i-th argument had an illegal value. If *INFO* = 1 on exit, then *LREF* has been set to the recommended length for the reference vector *REF*. If *INFO* = 0 then the reference vector, *REF*, has been successfully initialized.

Example:

```

C      Generate 100 values from the Multivariate Students T distribution
      INTEGER N, MM
      PARAMETER (N=100,MM=10)
      INTEGER I,J,INFO,SEED(1),STATE(15)
      INTEGER LDC,LDX,M,DF
      DOUBLE PRECISION X(N,MM),XMU(MM),C(MM,MM)
      INTEGER LREF
      DOUBLE PRECISION REF(1000)

C      Set array sizes
      LDC = MM
      LDX = N

C      Set the seed
      SEED(1) = 1234

C      Read in the distributional parameters
      READ(5,*) M,DF
      READ(5,*) (XMU(I),I=1,M)
      DO 20 I = 1,M
        READ(5,*) (C(I,J),J=1,M)
20    CONTINUE

C      Initialize the STATE vector
      CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C      Initialize the reference vector
      LREF = 1000
      CALL DRANDMULTISTUDENTSTREFERENCE(M,DF,XMU,C,LDC,REF,LREF,INFO)

C      Generate N variates from the Multivariate Students T distribution
      CALL DRANDMULTISTUDENTSTR(N,REF,STATE,X,LDX,INFO)

C      Print the results
      DO 40 I = 1,N
        WRITE(6,*) (X(I,J),J=1,M)
40    CONTINUE

```

### 6.3.4 Discrete Multivariate Distributions

#### DRANDMULTINOMIAL / SRANDMULTINOMIAL

Generates a matrix of random variates from a Multinomial distribution with probability,  $f(X)$ , defined by:

$$f(X) = \frac{M!}{\prod_{i=1}^K X_i!} \prod_{i=1}^K p_i^{X_i},$$

where  $X = \{X_1, X_2, \dots, X_K\}$ ,  $P = \{P_1, P_2, \dots, P_K\}$ ,  $\sum_{i=1}^K X_i = 1$  and  $\sum_{i=1}^K P_i = 1$ .

(Note that *SRANDMULTINOMIAL* is the single precision version of *DRANDMULTINOMIAL*. The argument lists of both routines are identical except that any double precision arguments of *DRANDMULTINOMIAL* are replaced in *SRANDMULTINOMIAL* by single precision arguments - type *REAL* in *FORTRAN* or type *float* in *C*).

DRANDMULTINOMIAL (N,M,P,K,STATE,X,LDX,INFO) [SUBROUTINE]

INTEGER N [Input]

On input: number of variates required.

Constraint:  $N \geq 0$ .

INTEGER M [Input]

On input: number of trials.

Constraint:  $M \geq 0$ .

DOUBLE PRECISION P(K) [Input]

On input: vector of probabilities for each of the  $K$  possible outcomes.

Constraint:  $0 \leq P_i \leq 1, i = 1, 2, \dots, K, \sum_{i=1}^K P_i = 1$ .

INTEGER K [Input]

On input: number of possible outcomes.

Constraint:  $K \geq 2$ .

INTEGER STATE(\*) [Input/Output]

The *STATE* vector holds information on the state of the base generator being used and as such its minimum length varies. Prior to calling *DRANDBINOMIAL* *STATE* must have been initialized. See [Section 6.1.1 \[Initialization of the Base Generators\]](#), page 66 for information on initialization of the *STATE* variable.

On input: the current state of the base generator.

On output: the updated state of the base generator.

INTEGER X(LDX,K) [Output]

On output: matrix of variates from the specified distribution.

INTEGER LDX

[Input]

On input: leading dimension of  $X$  in the calling routine.

Constraint:  $LDX \geq M$ .

INTEGER INFO

[Output]

On output: *INFO* is an error indicator. On successful exit, *INFO* contains 0.  
If  $INFO = -i$  on exit, the  $i$ -th argument had an illegal value.

Example:

```
C Generate 100 values from the Multinomial distribution
  INTEGER N, MK
  PARAMETER (N=100,MK=10)
  INTEGER I,J,INFO,SEED(1),STATE(15)
  INTEGER LDC,LDX,K,M
  INTEGER X(N,MK)
  DOUBLE PRECISION P(MK)

C Set array sizes
  LDX = N

C Set the seed
  SEED(1) = 1234

C Read in the distributional parameters
  READ(5,*) K
  READ(5,*) (P(I),I=1,K)

C Initialize the STATE vector
  CALL DRANDINITIALIZE(1,1,SEED,1,STATE,15,INFO)

C Generate N variates from the Multinomial distribution
  CALL DRANDMULTINOMIAL(N,M,P,K,STATE,X,LDX,INFO)

C Print the results
  DO 20 I = 1,N
    WRITE(6,*) (X(I,J),J=1,K)
  20 CONTINUE
```



## 7 ACML\_MV: Fast Math and Fast Vector Math Library

### 7.1 Introduction to ACML\_MV

ACML\_MV is a library which contains fast and/or vectorized versions of some familiar math library routines such as `sin`, `cos` and `exp`. The routines take advantage of the AMD64 architecture for performance, and so are currently only available with 64-bit versions of ACML. The routines in the library are very accurate over the range of acceptable input arguments.

Some of the performance is gained by sacrificing error handling or the acceptance of certain arguments. It is therefore the responsibility of the caller of these routines to ensure that their arguments are suitable. Furthermore, some of the routines are not callable from high-level languages at all, but must be called via assembly language; see the documentation of individual routines for details. Hence, these routines are intended to be utilized by knowledgeable users only.

#### 7.1.1 Terminology

The individual documentation for a routine states what outputs will be returned for special arguments, and also gives an indication of performance of the routine. In general, special case arguments for any routine will cause a return value in accordance with the C99 language standard [13].

Special case arguments include NaNs and infinities, as defined by the IEEE arithmetic standard [14]. In these documents, NaN means *Not a Number*, QNaN means *Quiet NaN*, and SNaN means *Signalling NaN*.

A *denormal* number is a number which is very tiny (close to the machine arithmetic underflow threshold) and is stored to less precision than a normal number. Due to their special nature, operations on such numbers are often very slow. While such numbers might not necessarily be regarded as special case arguments, for the sake of performance some of the ACML\_MV routines have been designed not to handle them. This has been noted in the documentation for each ACML\_MV routine.

Performance of a routine is given in machine cycles, and is thus independent of processor speed.

Accuracy of a routine is quoted in *ulps*, where *ulp* stands for *Unit in the Last Place*. Since floating-point numbers on a computer are limited precision approximations of mathematical numbers, not all real numbers can be represented by machine numbers, and the machine number must in general be rounded to available precision. An *ulp* is the distance between the two machine numbers that bracket a real number.

In this document, the *ulp* is used as a measure of the error in a returned result when compared with the mathematically exact expected result. Because of the finite nature of machine arithmetic, a routine can never in general achieve accuracy of better than 0.5 *ulps*, and an accuracy of less than 1 *ulp* is good.

#### 7.1.2 Weak Aliases

Some of the functions in ACML\_MV include a weak alias to an equivalent function in `libm`. For example, the `fastcos` function includes a weak alias to `cos`. If ACML\_MV is included in

the link order before libm, then all calls to the aliased libm function name (e.g. `cos`) will use the equivalent ACML\_MV routine (e.g. `fastcos`). If ACML\_MV is included in the link order after libm, then all calls to libm functions will use the libm versions.

ACML\_MV routines can always be accessed using their ACML\_MV names (e.g. `fastcos`), regardless of link order.

### 7.1.3 Defined Types

The following types are used to describe the functions contained in this chapter:

`--m128d`    a pair of double precision values;  
`--m128`     four single precision values.

## 7.2 Fast Basic Math Functions

This section documents the interfaces to a set of basic mathematical functions.

### fastcos: fast double precision Cosine

`double fastcos (double x)`

Weak alias: `cos`

C Prototype:

`double fastcos (double x);`

Inputs:

double x - the double precision input value.

Outputs:

Cosine of x.

Fortran Function Interface:

DOUBLE PRECISION FASTCOS(X)

Inputs:

DOUBLE PRECISION X - the double precision input value.

Return Value:

Cosine of X.

Notes:

`fastcos` computes the Cosine function of its argument x.

This is a *relaxed* version of `cos`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 2 ulp over most of the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

88 cycles for most valid inputs < 5e5.

**fastcosf: fast single precision Cosine****float fastcosf** (*float* x)

Weak alias: cosf

C Prototype:

float fastcosf (float x);

Inputs:

float x - the single precision input value.

Outputs:

Single precision Cosine of x.

Fortran Function Interface:

REAL FASTCOSF(X)

Inputs:

REAL X - the single precision input value.

Return Value:

Cosine of X.

Notes:

fastcosf computes the single precision Cosine function of its argument x.

This is a *relaxed* version of cosf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 ulp over most of the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

91 cycles for most valid inputs &lt; 5e5.

**fastexp: fast double precision exponential function****double fastexp** (*double x*)Weak alias: `exp`

C Prototype:

`double fastexp (double x);`

Inputs:

`double x` - the double precision input value.

Outputs:

`e` raised to the power `x` (exponential of `x`).

Fortran Function Interface:

`DOUBLE PRECISION FASTEXP(X)`

Inputs:

`DOUBLE PRECISION X` - the double precision input value.

Return Value:

`e` raised to the power `X` (exponential of `X`).

Notes:

`fastexp` computes the double precision exponential function of the input argument `x`.

This is a *relaxed* version of `exp`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -708.5$	0
$> 709.8$	$+\infty$

Performance:

75 cycles for most valid inputs.

**fastexpf: fast single precision exponential function****float fastexpf** (*float* x)

Weak alias: expf

C Prototype:

float fastexpf (float x);

Inputs:

float x - the single precision input value.

Outputs:

e raised to the power x (exponential of x).

Fortran Function Interface:

REAL FASTEXP(X)

Inputs:

REAL X - the single precision input value.

Return Value:

e raised to the power X (exponential of X).

Notes:

fastexpf computes the single precision exponential function of the input argument x.

This is a *relaxed* version of expf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -87.5$	0
$> 88$	$+\infty$

Performance:

75 cycles for most valid inputs.

**fastlog: fast double precision natural logarithm function**

`double fastlog (double x)`

Weak alias: `log`

C Prototype:

`double fastlog (double x);`

Inputs:

double x - the double precision input value.

Outputs:

The natural logarithm (base e) of x.

Fortran Function Interface:

DOUBLE PRECISION FASTLOG(X)

Inputs:

DOUBLE PRECISION X - the double precision input value.

Return Value:

The natural logarithm (base e) of X.

Notes:

`fastlog` computes the double precision natural logarithm of its argument x.

This is a *relaxed* version of `log`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

97 cycles for most valid inputs.

86 cycles for  $.97 < x < 1.03$

**fastlogf: fast single precision natural logarithm function**

**float fastlogf** (*float* x)

Weak alias: logf

C Prototype:

`float fastlogf (float x);`

Inputs:

`float x` - the single precision input value.

Outputs:

The natural logarithm (base e) of x.

Fortran Function Interface:

`REAL FASTLOGF(X)`

Inputs:

`REAL X` - the single precision input value.

Return Value:

The natural logarithm (base e) of X.

Notes:

fastlogf computes the single precision natural logarithm of its argument x.

This is a *relaxed* version of logf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

94 cycles for most valid inputs.

85 cycles for  $.97 < x < 1.03$



**fastlog10: fast double precision base-10 logarithm function****double fastlog10** (*double x*)

Weak alias: log10

C Prototype:

double fastlog10 (double x);

Inputs:

double x - the double precision input value.

Outputs:

The base-10 logarithm of x.

Fortran Function Interface:

DOUBLE PRECISION FASTLOG10(X)

Inputs:

DOUBLE PRECISION X - the double precision input value.

Return Value:

The base-10 logarithm of X.

Notes:

fastlog10 computes the double precision base-10 logarithm of its argument x.

This is a *relaxed* version of log10, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

112 cycles for most valid inputs.

**fastlog10f: fast single precision base-10 logarithm function**

`float fastlog10f (float x)`

Weak alias: `log10f`

C Prototype:

`float fastlog10f (float x);`

Inputs:

`float x` - the single precision input value.

Outputs:

The base-10 logarithm of `x`.

Fortran Function Interface:

`REAL FASTLOG10F(X)`

Inputs:

`REAL X` - the single precision input value.

Return Value:

The base-10 logarithm of `X`.

Notes:

`fastlog10f` computes the single precision base-10 logarithm of its argument `x`.

This is a *relaxed* version of `log10f`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

104 cycles for most valid inputs.

**fastpow: fast double precision power function**

**double fastpow** (*double x, double y*)

Weak alias: pow

C Prototype:

double fastpow (double x, double y);

Inputs:

double x - the double precision base input value.

double y - the double precision exponent input value.

Outputs:

x raised to the power y.

Fortran Function Interface:

DOUBLE PRECISION FASTPOW(X,Y)

Inputs:

DOUBLE PRECISION X - the base value.

DOUBLE PRECISION Y - the exponent value.

Return Value:

X raised to the power Y.

Notes:

fastpow computes the x raised to the power y in double precision.

This is a *relaxed* version of pow, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs will produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input <i>x</i></b>	<b>Input <i>y</i></b>	<b>Output</b>
$\pm 0$	$y < 0$ , odd integer	$\pm\infty$
$\pm 0$	$y < 0$ , not odd integer	$+\infty$
$\pm 0$	$y > 0$ , odd integer	$\pm 0$
$\pm 0$	$y > 0$ , not odd integer	$+0$
$-1$	$+\infty$	$1$
$+1$	$y$ (incl. NaN)	$1$
$x$ (incl. Nan)	$\pm 0$	$1$
$x < 0$	$y$ , not integer	<i>QNaN</i>
$ x  < 1$	$-\infty$	$+\infty$
$ x  > 1$	$-\infty$	$+0$
$ x  < 1$	$+\infty$	$+0$
$ x  > 1$	$+\infty$	$+\infty$
$-\infty$	$y < 0$ , odd integer	$-0$
$-\infty$	$y < 0$ , not odd integer	$+0$

$-\infty$	$y > 0$ , odd integer	$-\infty$
$-\infty$	$y > 0$ , not odd integer	$+\infty$
$+\infty$	$y < 0$ ,	$+0$
$+\infty$	$y > 0$ ,	$+\infty$
$NaN$	$y$ nonzero,	$NaN$
$x <> 1$	$NaN$ ,	$NaN$

Performance:

200 cycles for most valid inputs.

**fastpowf: fast single precision power function**

`float fastpowf (float x, float y)`

Weak alias: `powf`

C Prototype:

`float fastpowf (float x, float y);`

Inputs:

float x - the single precision base input value.

float y - the single precision exponent input value.

Outputs:

x raised to the power y.

Fortran Function Interface:

`REAL FASTPOWF(X,Y)`

Inputs:

REAL X - the single precision base value.

REAL Y - the single precision exponent value.

Return Value:

X raised to the power Y.

Notes:

`fastpowf` computes the x raised to the power y in single precision.

This is a *relaxed* version of `powf`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs will produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 0.5 *ulp* over the valid input range.

Special case return values:

Input <i>x</i>	Input <i>y</i>	Output
$\pm 0$	$y < 0$ , odd integer	$\pm\infty$
$\pm 0$	$y < 0$ , not odd integer	$+\infty$
$\pm 0$	$y > 0$ , odd integer	$\pm 0$
$\pm 0$	$y > 0$ , not odd integer	$+0$
$-1$	$+\infty$	$1$
$+1$	$y$ (incl. NaN)	$1$
$x$ (incl. Nan)	$\pm 0$	$1$
$x < 0$	$y$ , not integer	<i>QNaN</i>
$ x  < 1$	$-\infty$	$+\infty$
$ x  > 1$	$-\infty$	$+0$
$ x  < 1$	$+\infty$	$+0$
$ x  > 1$	$+\infty$	$+\infty$
$-\infty$	$y < 0$ , odd integer	$-0$
$-\infty$	$y < 0$ , not odd integer	$+0$

$-\infty$	$y > 0$ , odd integer	$-\infty$
$-\infty$	$y > 0$ , not odd integer	$+\infty$
$+\infty$	$y < 0$ ,	$+0$
$+\infty$	$y > 0$ ,	$+\infty$
$NaN$	$y$ nonzero,	$NaN$
$x<>1$	$NaN$ ,	$NaN$

Performance:

175 cycles for most valid inputs.

**fastsin: fast double precision Sine****double fastsin** (*double x*)

Weak alias: sin

C Prototype:

double fastsin (double x);

Inputs:

double x - the double precision input value.

Outputs:

Sine of x.

Fortran Function Interface:

DOUBLE PRECISION FASTSIN(X)

Inputs:

DOUBLE PRECISION X - the double precision input value.

Return Value:

Sine of X.

Notes:

fastsin computes the Sine function of its argument x.

This is a *relaxed* version of sin, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

88 cycles for most valid inputs &lt; 5e5.

**fastsinf: fast single precision Sine**

`float fastsinf (float x)`

Weak alias: `sinf`

C Prototype:

`float fastsinf (float x);`

Inputs:

`float x` - the single precision input value.

Outputs:

Single precision Sine of `x`.

Fortran Function Interface:

`REAL PRECISION FASTSINF(X)`

Inputs:

`REAL PRECISION X` - the single precision input value.

Return Value:

Sine of `X`.

Notes:

`fastsinf` computes the Sine function of its argument `x`.

This is a *relaxed* version of `sinf`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

88 cycles for most valid inputs < 5e5.



**fastsincos: fast double precision Sine and Cosine**

**void fastsincos** (*double x, double s, double c*)

Weak alias: sincos

C Prototype:

```
void fastsincos (double x, double s, double c);
```

Inputs:

double x - the double precision input value.

Outputs:

double s - Sine of x.

double c - Cosine of x.

Fortran Subroutine Interface:

```
SUBROUTINE FASTSINCOS(X,S,C)
```

Inputs:

DOUBLE PRECISION X - the double precision input value.

Outputs:

DOUBLE PRECISION S - Sine of X.

DOUBLE PRECISION C - Cosine of X.

Notes:

fastsincos computes the Sine and Cosine functions of its argument x.

This function can provide a significant performance advantage for applications that require both the sine and cosine of an angle, such as axis and matrix rotation. This is a *relaxed* version of sincos, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

99 cycles for most valid inputs < 5e5.

**fastsincosf: fast single precision Sine and Cosine**

**void fastsincosf** (*float x, float s, float c*)

Weak alias: sincosf

C Prototype:

void fastsincosf (float x, float s, float c);

Inputs:

float x - the single precision input value.

Outputs:

float s - Sine of x.

float c - Cosine of x.

Fortran Subroutine Interface:

SUBROUTINE FASTSINCOSF(X,S,C)

Inputs:

REAL X - the single precision input value.

Outputs:

REAL S - Sine of X.

REAL C - Cosine of X.

Notes:

fastsincosf computes the Sine and Cosine functions of its argument x.

This function can provide a significant performance advantage for applications that require both the sine and cosine of an angle, such as axis and matrix rotation. This is a *relaxed* version of sincosf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Error inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

91-102 cycles for most valid inputs < 5e5.

## 7.3 Fast Vector Math Functions

This section documents the interfaces to a set of vector mathematical functions.

### **vr2d\_cos: Two-valued double precision Cosine**

`--m128d __vr2d_cos (--m128d x)`

C Prototype:

```
--m128d __vr2d_cos(--m128d x);
```

Inputs:

--m128d x - the double precision input value pair.

Outputs:

--m128d y - the double precision Cosine result pair, returned in xmm0.

Notes:

--vr2d\_cos computes the Cosine function of two input arguments.

This routine accepts a pair of double precision input values passed as a --m128d value. The result is the double precision Cosine of both values, returned as a --m128d value. This is a *relaxed* version of cos, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

120 cycles for most valid inputs < 5e5 (60 cycles per value).

**vr4d\_cos: Four-valued double precision Cosine**

```
__m128d, __m128d  __vr4d_cos (__m128d x1, __m128d x2)
```

C Prototype:

```
__m128d __vr2_cos(__m128d x);
```

Note that this function uses a non-standard programming interface. The two `__m128d` inputs, which contain four double precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128d` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128d x1` - the first double precision input value pair.

`__m128d x2` - the second double precision input value pair.

Outputs:

`__m128d y1` - the first double precision Cosine result pair, returned in `xmm0`.

`__m128d y2` - second double precision Cosine result pair, returned in `xmm1`.

Notes:

`__vr4d_cos` computes the Cosine function of four input arguments.

This routine accepts four double precision input values passed as two `__m128d` values. The result is the double precision Cosine of the four values, returned as two `__m128d` values. This is a *relaxed* version of `cos`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

172 cycles for most valid inputs < 5e5 (43 cycles per value).

**vrda\_cos: Array double precision Cosine**

```
void vrda_cos (int n, double *x, double *y)
```

C Prototype:

```
void vrda_cos (int n, double *x, double *y)
```

Inputs:

```

int      n      - the number of values in both the input and output arrays.
double   *x      - pointer to the array of input values.
double   *y      - pointer to the array of output values.
```

Outputs:

Cosine for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_COS(N,X,Y)
```

Inputs:

```

INTEGER N - the number of values in both the input and output arrays.
DOUBLE PRECISION X(N) - array of double precision input values.
```

Outputs:

```
DOUBLE PRECISION Y(N) - array of Cosines of input values.
```

Notes:

vrda\_cos computes the Cosine function for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes  $\cos(x)$  for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of cos, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

172 cycles for most valid inputs < 5e5 (43 cycles per value), n = 24.

**vrs4\_csf: Four-valued single precision Cosine**

`__m128 __vrs4_csf (__m128 x)`

C Prototype:

```
__m128 __vrs4_csf(__m128 x);
```

Inputs:

`__m128 x` - the four single precision input values.

Outputs:

`__m128 y` - the four single precision Cosine results , returned in `xmm0`.

Notes:

`__vrs4_csf` computes the Cosine function of four input arguments.

This routine accepts four single precision input values passed as a `__m128` value. The result is the single precision Cosine of all four values, returned as a `__m128` value. This is a *relaxed* version of `cosf`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

176 cycles for most valid inputs < 5e5 (44 cycles per value).

**vrsa\_cosf: Array single precision Cosine**

```
void vrsa_cosf (int n, float *x, float *y)
```

C Prototype:

```
void vrsa_cosf (int n, float *x, float *y)
```

Inputs:

```

int      n      - the number of values in both the input and output arrays.
float    *x      - pointer to the array of input values.
float    *y      - pointer to the array of output values.
```

Outputs:

Cosine for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_COSF(N,X,Y)
```

Inputs:

```

INTEGER N - the number of values in both the input and output arrays.
REAL X(N) - array of single precision input values.
```

Outputs:

```
REAL Y(N) - array of Cosines of input values.
```

Notes:

vrsa\_cosf computes the Cosine function for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes cosf(x) for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of cosf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

43 cycles per value for most valid inputs < 5e5, n = 24.

**vr2d\_exp: Two-valued double precision exponential function****\_\_m128d \_\_vr2d\_exp (\_\_m128d x)**

C Prototype:

`__m128d __vr2d_exp(__m128d x);`

Inputs:

`__m128d x` - the double precision input value pair.

Outputs:

 $e$  raised to the power  $x$  (exponential of  $x$ ).`__m128d y` - the double precision exponent result pair, returned in `xmm0`.

Notes:

`__vr2d_exp` computes the exponential function of two input arguments.

This routine accepts a pair of double precision input values passed as a `__m128d` value. The result is the double precision exponent of both values, returned as a `__m128d` value. This is a *relaxed* version of `exp`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -708.5$	0
$> 709.8$	$+\infty$

Performance:

80 cycles for most valid inputs (40 cycles per value).



**vr4d\_exp: Four-valued double precision exponential function**

```
__m128d, __m128d __vr4d_exp (__m128d x1, __m128d x2)
```

Prototype:

```
__m128d, __m128d __vr4d_exp(__m128d x1, __m128d x2);
```

Note that this function uses a non-standard programming interface. The two `__m128d` inputs, which contain four double precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128d` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128d x1` - the first double precision input value pair.

`__m128d x2` - the second double precision input value pair.

Outputs:

`__m128d y1` - the first double precision exponent result pair, returned in `xmm0`.

`__m128d y2` - the second double precision exponent result pair, returned in `xmm1`.

Notes:

`__vr4d_exp` computes the double precision exponential function of four input arguments.

This routine accepts four double precision input values passed as two `__m128d` values. The result is the double precision exponent of the four values, returned as two `__m128d` values. This is a *relaxed* version of `exp`, suitable for use with fast-math compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -708.5$	0
$> 709.8$	$+\infty$

Performance:

132 cycles for most valid inputs (33 cycles per value).

**vrda\_exp: Array double precision exponential function**

```
void vrda_exp (int n, double *x, double *y)
```

C Prototype:

```
void vrda_exp (int n, double *x, double *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
double	*x	- pointer to the array of input values.
double	*y	- pointer to the array of output values.

Outputs:

e raised to the power x (exponential of x) for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_EXP(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
DOUBLE PRECISION	X(N)	- array of double precision input values.

Outputs:

DOUBLE PRECISION	Y(N)	- array of exponentials (e raised to the power x) of input values.
------------------	------	--

Notes:

vrda\_exp computes the double precision exponential function for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes the  $e^x$  for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of exp, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -708.5$	0
$> 709.8$	$+\infty$

Performance:

33 cycles per value for valid inputs, n = 24.

**vrs4\_expf: Four-valued single precision exponential function**`__m128 __vrs4_expf (__m128 x)`

C Prototype:

`__m128 __vrs4_expf(__m128 x);`

Inputs:

`__m128 x` - the four single precision input values.

Outputs:

e raised to the power x (exponential of x) for each input value x.

`__m128 y` - the four single precision exponent results, returned in `xmm0`.

Notes:

`__vrs4_expf` computes the double precision exponential function of four input arguments.

This routine accepts four single precision input values passed as a `__m128` value. The result is the single precision exponent of the four values, returned as a `__m128` value. This is a *relaxed* version of `exp`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -87.5$	0
$> 88$	$+\infty$

Performance:

91 cycles for most valid inputs (23 cycles per value).

**vrs8\_expf: Eight-valued single precision exponential function**

```
__m128, __m128 __vrs8_expf (__m128 x1, __m128 x2)
```

Prototype:

```
__m128, __m128 __vrs8_expf(__m128 x1, __m128 x2);
```

Note that this function uses a non-standard programming interface. The two `__m128` inputs, which contain eight single precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128 x1` - the first single precision vector of four input values.

`__m128 x2` - the second single precision vector of four input values.

Outputs:

`__m128 y1` - the first four single precision exponent results, returned in `xmm0`.

`__m128 y2` - the second four single precision exponent results, returned in `xmm1`.

Notes:

`__vrs8_expf` computes the single precision exponential function of eight input arguments.

This routine accepts eight single precision input values passed as two `__m128` values. The result is the single precision exponent of the eight values, returned as two `__m128` values. This is a *relaxed* version of `exp`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -87.5$	0
$> 88$	$+\infty$

Performance:

155 cycles for most valid inputs (19 cycles per value).

**vrsa\_expf: Array single precision exponential function**

```
void vrsa_expf (int n, float *x, float *y)
```

C Prototype:

```
void vrsa_expf (int n, float *x, float *y)
```

Inputs:

int        n    - the number of single precision values in both the input and output arrays.  
float     \*x    - pointer to the array of input values.  
float     \*y    - pointer to the array of output values.

Outputs:

e raised to the power x (exponential of x) for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_EXPF(N,X,Y)
```

Inputs:

INTEGER N - the number of values in both the input and output arrays.  
REAL X(N) - array of single precision input values.

Outputs:

REAL Y(N) - array of exponentials (e raised to the power x) of input values.

Notes:

vrsa\_expf computes the single precision exponential function for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes the  $e^x$  for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of exp, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$< -87.5$	0
$> 88$	$+\infty$

Performance:

15 cycles per value for valid inputs,  $n = 24$ .

**vr2\_log: Two-valued double precision natural logarithm****\_\_m128d \_\_vr2\_log (\_\_m128d x)**

C Prototype:

**\_\_m128d \_\_vr2\_log(\_\_m128d x);**

Inputs:

**\_\_m128d x** - the double precision input value pair.

Outputs:

The natural (base e) logarithm of **x**.**\_\_m128d y** - the double precision natural logarithm result pair, returned in **xmm0**.

Notes:

**\_\_vr2\_log** computes the natural logarithm for each of two input arguments.

This routine accepts a pair of double precision input values passed as a **\_\_m128d** value. The result is the double precision natural logarithm of both values, returned as a **\_\_m128d** value. This is a *relaxed* version of **log**, suitable for use with **fastmath** compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

130 cycles for most valid inputs (65 cycles per value).

**vr4\_log: Four-valued double precision natural logarithm**

```
__m128d, __m128d __vr4_log (__m128d x1, __m128d x2)
```

Prototype:

```
__m128d, __m128d __vr4_log(__m128d x1, __m128d x2);
```

Note that this function uses a non-standard programming interface. The two `__m128d` inputs, which contain four double precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128d` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128d x1` - the first double precision input value pair.

`__m128d x2` - the second double precision input value pair.

Outputs:

The natural (base *e*) logarithm of *x*.

`__m128d y1` - the first double precision natural logarithm result pair, returned in `xmm0`.

`__m128d y2` - the second double precision natural logarithm result pair, returned in `xmm1`.

Notes:

`__vr4_log` computes the natural logarithm for each of four input arguments.

This routine accepts four double precision input values passed as two `__m128d` values. The result is the double precision natural logarithm of the four values, returned as two `__m128d` values. This is a *relaxed* version of `log`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

196 cycles for most valid inputs (49 cycles per value).

**vrda\_log: Array double precision natural logarithm**

```
void vrda_log (int n, double *x, double *y)
```

C Prototype:

```
void vrda_log (int n, double *x, double *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
double	*x	- pointer to the array of input values.
double	*y	- pointer to the array of output values.

Outputs:

The natural (base e) logarithm of each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_LOG(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
DOUBLE PRECISION	X(N)	- array of double precision input values.

Outputs:

DOUBLE PRECISION	Y(N)	- array of natural (base e) logarithms of input values.
------------------	------	---

Notes:

vrda\_log computes the double precision natural logarithm for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes the natural log for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of log, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>



Performance:

51 cycles per value for valid inputs,  $n = 24$ .

**vrs4\_logf: Four-valued single precision natural logarithm****\_\_m128 \_\_vrs4\_logf (\_\_m128 x)**

C Prototype:

**\_\_m128 \_\_vrs4\_logf(\_\_m128 x);**

Inputs:

**\_\_m128 x** - the single precision input values.

Outputs:

The natural (base e) logarithm of x.

**\_\_m128 y** - the single precision natural logarithm results, returned in xmm0.

Notes:

**\_\_vrs4\_logf** computes the natural logarithm for each of four input arguments.

This routine accepts four single precision input values passed as a **\_\_m128** value. The result is the single precision natural logarithm of all four values, returned as a **\_\_m128** value. This is a *relaxed* version of **logf**, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

124 cycles for most valid inputs (31 cycles per value).

**vrs8\_logf: Eight-valued single precision natural logarithm**

```
__m128, __m128 __vrs8_logf (__m128 x1, __m128 x2)
```

Prototype:

```
__m128, __m128 __vrs8_logf(__m128 x1, __m128 x2);
```

Note that this function uses a non-standard programming interface. The two `__m128` inputs, which contain eight single precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128 x1` - the first single precision input value pair.

`__m128 x2` - the second single precision input value pair.

Outputs:

The natural (base *e*) logarithm of *x*.

`__m128 y1` - the first single precision natural logarithm result pair, returned in `xmm0`.

`__m128 y2` - the second single precision natural logarithm result pair, returned in `xmm1`.

Notes:

`__vrs8_logf` computes the natural logarithm for each of eight input arguments.

This routine accepts eight single precision input values passed as two `__m128` values. The result is the single precision natural logarithm of the eight values, returned as two `__m128` values. This is a *relaxed* version of `logf`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

200 cycles for most valid inputs (25 cycles per value).

**vrsa\_logf: Array single precision natural logarithm**

```
void vrsa_logf (int n, float *x, float *y)
```

C Prototype:

```
void vrsa_logf (int n, float *x, float *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
float	*x	- pointer to the array of input values.
float	*y	- pointer to the array of output values.

Outputs:

The natural (base e) logarithm of each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_LOGF(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
REAL	X(N)	- array of single precision input values.

Outputs:

REAL	Y(N)	- array of natural (base e) logarithms of input values.
------	------	---

Notes:

vrsa\_logf computes the single precision natural logarithm for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes the natural log for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of logf, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

26 cycles per value for valid inputs, n = 24.

**vr2\_log10: Two-valued double precision base-10 logarithm****\_\_m128d \_\_vr2\_log10 (\_\_m128d x)**

C Prototype:

`__m128d __vr2_log10(__m128d x);`

Inputs:

`__m128d x` - the double precision input value pair.

Outputs:

The base-10 logarithm of `x`.`__m128d y` - the double precision base-10 logarithm result pair, returned in `xmm0`.

Notes:

`__vr2_log10` computes the base-10 logarithm for each of two input arguments.

This routine accepts a pair of double precision input values passed as a `__m128d` value. The result is the double precision base-10 logarithm of both values, returned as a `__m128d` value. This is a *relaxed* version of `log10`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

142 cycles for most valid inputs (71 cycles per value), longer for input values very close to 1.0.

**vr4\_log10: Four-valued double precision base-10 logarithm**

```
__m128d, __m128d __vr4_log10 (__m128d x1, __m128d x2)
```

Prototype:

```
__m128d, __m128d __vr4_log10(__m128d x1, __m128d x2);
```

Note that this function uses a non-standard programming interface. The two `__m128d` inputs, which contain four double precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128d` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128d x1` - the first double precision input value pair.

`__m128d x2` - the second double precision input value pair.

Outputs:

The base-10 logarithm of `x`.

`__m128d y1` - the first double precision base-10 logarithm result pair, returned in `xmm0`.

`__m128d y2` - the second double precision base-10 logarithm result pair, returned in `xmm1`.

Notes:

`__vr4_log10` computes the base-10 logarithm for each of four input arguments.

This routine accepts four double precision input values passed as two `__m128d` values. The result is the double precision base-10 logarithm of the four values, returned as two `__m128d` values. This is a *relaxed* version of `log10`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

235 cycles for most valid inputs (59 cycles per value), longer for input values very close to 1.0.

**vrda\_log10: Array double precision base-10 logarithm**

```
void vrda_log10 (int n, double *x, double *y)
```

C Prototype:

```
void vrda_log10 (int n, double *x, double *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
double	*x	- pointer to the array of input values.
double	*y	- pointer to the array of output values.

Outputs:

The base-10 logarithm of each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_LOG10(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
DOUBLE PRECISION	X(N)	- array of double precision input values.

Outputs:

DOUBLE PRECISION	Y(N)	- array of base-10 logarithms of input values.
------------------	------	--

Notes:

vrda\_log10 computes the double precision base-10 logarithm for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes the base-10 log for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of log10, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:



54 cycles per value for valid inputs,  $n = 24$ , longer for input values very close to 1.0.

**vrs4\_log10f: Four-valued single precision base-10 logarithm**`__m128 __vrs4_log10f (__m128 x)`

Prototype:

`__m128 __vrs4_log10f(__m128 x);`

Inputs:

`__m128 x` - the four single precision inputs.

Outputs:

The base-10 logarithm of `x`.`__m128 y` - the four single precision base-10 logarithm results, returned in `xmm0`.

Notes:

`__vrs4_log10f` computes the base-10 logarithm for each of four input arguments.

This routine accepts four single precision input values passed as a `__m128` value. The result is the single precision base-10 logarithm of the four values, returned as a `__m128` value. This is a *relaxed* version of `log10`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

141 cycles for most valid inputs (35 cycles per value), longer for input values very close to 1.0.

**vrs8\_log10f: Eight-valued single precision base-10 logarithm**

```
__m128, __m128 __vrs8_log10f (__m128 x1, __m128 x2)
```

Prototype:

```
__m128, __m128 __vrs8_log10f(__m128 x1, __m128 x2);
```

Note that this function uses a non-standard programming interface. The two `__m128` inputs, which contain eight single precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128 x1` - the first set of four single precision input values.

`__m128 x2` - the second set of four single precision input values.

Outputs:

The base-10 logarithm of `x`.

`__m128 y1` - the first set of four single precision base-10 logarithm results, returned in `xmm0`.

`__m128 y2` - the second set of four single precision base-10 logarithm results, returned in `xmm1`.

Notes:

`__vrs8_log10f` computes the base-10 logarithm for each of eight input arguments.

This routine accepts eight single precision input values passed as two `__m128` values. The result is the single precision base-10 logarithm of the eight values, returned as two `__m128` values. This is a *relaxed* version of `log10f`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

231 cycles for most valid inputs (29 cycles per value), longer for input values very close to 1.0.

**vrса\_log10f: Array single precision base-10 logarithm**

```
void vrса_log10f (int n, float *x, float *y)
```

C Prototype:

```
void vrса_log10f (int n, float *x, float *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
float	*x	- pointer to the array of input values.
float	*y	- pointer to the array of output values.

Outputs:

The base-10 logarithm of each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_LOG10F(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
REAL	X(N)	- array of single precision input values.

Outputs:

REAL	Y(N)	- array of base-10 logarithms of input values.
------	------	--

Notes:

vrса\_log10f computes the single precision base-10 logarithm for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes the base-10 log for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of log10f, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
$\pm 0$	$-\infty$
negative	<i>QNaN</i>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	$+\infty$
$-\infty$	<i>QNaN</i>

Performance:

28 cycles per value for valid inputs,  $n = 24$ , longer for input values very close to 1.0.

**vrs4\_powf: Four-valued single precision power function**

`__m128 __vrs4_powf (__m128 x, __m128 y)`

C Prototype:

```
__m128 __vrs4_powf(__m128 x, __m128 y);
```

Inputs:

`__m128 x` - the single precision input base values.

`__m128 y` - the single precision input exponent values.

Outputs:

`__m128 z` - the single precision results of each `x` raised to the `y` power, returned in `xmm0`.

Notes:

`__vrs4_powf()` computes the single precision `x` raised to the `y` power for four pairs of input arguments. This routine accepts four single precision input value pairs passed as `__m128` values. The result is the `x` raised to the `y` power for all four input pairs, returned as a `__m128` value.

This is a *relaxed* version of `powf`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 0.5 *ulp* over the valid input range.

Special case return values:

Input <i>x</i>	Input <i>y</i>	Output
$\pm 0$	$y < 0$ , odd integer	$\pm\infty$
$\pm 0$	$y < 0$ , not odd integer	$+\infty$
$\pm 0$	$y > 0$ , odd integer	$\pm 0$
$\pm 0$	$y > 0$ , not odd integer	$+0$
$-1$	$+\infty$	$1$
$+1$	$y$ (incl. NaN)	$1$
$x$ (incl. Nan)	$\pm 0$	$1$
$x < 0$	$y$ , not integer	<i>QNaN</i>
$ x  < 1$	$-\infty$	$+\infty$
$ x  > 1$	$-\infty$	$+0$
$ x  < 1$	$+\infty$	$+0$
$ x  > 1$	$+\infty$	$+\infty$
$-\infty$	$y < 0$ , odd integer	$-0$
$-\infty$	$y < 0$ , not odd integer	$+0$
$-\infty$	$y > 0$ , odd integer	$-\infty$
$-\infty$	$y > 0$ , not odd integer	$+\infty$
$+\infty$	$y < 0$ ,	$+0$
$+\infty$	$y > 0$ ,	$+\infty$
NaN	$y$ nonzero,	NaN
$x <> 1$	NaN,	NaN

Performance:

400 cycles for most valid inputs (100 cycles per value).



## vrs4\_powxf: Four-valued single precision power function with constant y

`--m128 __vrs4_powxf (--m128 x,float y)`

C Prototype:

```
--m128 __vrs4_powxf(--m128 x,float y);
```

Inputs:

--m128 x - the single precision input base values.

float y - the common single precision input exponent value.

Outputs:

--m128 z - the single precision results of each x raised to the y power, returned in xmm0.

Notes:

`--vrs4_powxf()` computes the single precision x raised to the y power for four input x arguments and a constant y input value. This routine accepts four single precision input values passed as an `--m128` value. The y value is passed as one single precision value. The result is the x raised to the y power for all four input values, returned as a `--m128` value.

This is a *relaxed* version of `powxf`, suitable for use with `fastmath` compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 0.5 *ulp* over the valid input range.

Special case return values:

Input x	Input y	Output
$\pm 0$	$y < 0$ , odd integer	$\pm\infty$
$\pm 0$	$y < 0$ , not odd integer	$+\infty$
$\pm 0$	$y > 0$ , odd integer	$\pm 0$
$\pm 0$	$y > 0$ , not odd integer	$+0$
-1	$+\infty$	1
+1	y (incl. NaN)	1
x (incl. Nan)	$\pm 0$	1
$x < 0$	y, not integer	QNaN
$ x  < 1$	$-\infty$	$+\infty$
$ x  > 1$	$-\infty$	$+0$
$ x  < 1$	$+\infty$	$+0$
$ x  > 1$	$+\infty$	$+\infty$
$-\infty$	$y < 0$ , odd integer	$-0$
$-\infty$	$y < 0$ , not odd integer	$+0$
$-\infty$	$y > 0$ , odd integer	$-\infty$
$-\infty$	$y > 0$ , not odd integer	$+\infty$
$+\infty$	$y < 0$ ,	$+0$
$+\infty$	$y > 0$ ,	$+\infty$
NaN	y nonzero,	NaN

$x < > 1$                        $NaN$ ,                       $NaN$

Performance:

372 cycles for most valid inputs (93 cycles per value).

**vr2\_sin: Two-valued double precision Sine****\_\_m128d \_\_vr2\_sin (\_\_m128d x)**

C Prototype:

`__m128d __vr2_sin(__m128d x);`

Inputs:

`__m128d x` - the double precision input value pair.

Outputs:

`__m128d y` - the double precision Sine result pair, returned in `xmm0`.

Notes:

`__vr2_sin` computes the Sine function of two input arguments.

This routine accepts a pair of double precision input values passed as a `__m128d` value. The result is the double precision Sine of both values, returned as a `__m128d` value. This is a *relaxed* version of `sin`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

120 cycles for most valid inputs &lt; 5e5 (60 cycles per value).

**vrd4\_sin: Four-valued double precision Sine**

```
__m128d, __m128d __vrd4_sin (__m128d x1, __m128d x2)
```

C Prototype:

```
__m128d __vrd4_sin(__m128d x);
```

Note that this function uses a non-standard programming interface. The two `__m128d` inputs, which contain four double precision values, are passed by the AMD64 C ABI in registers `xmm0`, and `xmm1`. The corresponding results are returned in `xmm0` and `xmm1`. The use of `xmm1` to return a `__m128d` is non-standard, and this function can not be called directly from C. It can be called directly from assembly language. It is intended for internal use by vectorizing compilers, that may be able to take advantage of the non-standard calling interface.

Inputs:

`__m128d x1` - the first double precision input value pair.

`__m128d x2` - the second double precision input value pair.

Outputs:

`__m128d y1` - the first double precision Sine result pair, returned in `xmm0`.

`__m128d y2` - second double precision Sine result pair, returned in `xmm1`.

Notes:

`__vrd4_sin` computes the Sine function of four input arguments.

This routine accepts four double precision input values passed as two `__m128d` values. The result is the double precision Sine of the four values, returned as two `__m128d` values. This is a *relaxed* version of `sin`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range. This routine may return slightly worse than 1 *ulp* for very large values between  $4e5$  and  $5e5$ .

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

172 cycles for most valid inputs  $< 5e5$  (43 cycles per value).

**vrda\_sin: Array double precision Sine**

```
void vrda_sin (int n, double *x, double *y)
```

C Prototype:

```
void vrda_sin (int n, double *x, double *y)
```

Inputs:

```

int      n    - the number of values in both the input and output arrays.
double   *x    - pointer to the array of input values.
double   *y    - pointer to the array of output values.
```

Outputs:

Sine for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_SIN(N,X,Y)
```

Inputs:

```

INTEGER N - the number of values in both the input and output arrays.
DOUBLE PRECISION X(N) - array of double precision input values.
```

Outputs:

```
DOUBLE PRECISION Y(N) - array of Sines of input values.
```

Notes:

vrda\_sin computes the Sine function for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes  $\sin(x)$  for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of sin, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range. This routine may return slightly worse than 1 *ulp* for very large values between  $4e5$  and  $5e5$ .

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

172 cycles for most valid inputs  $< 5e5$  (43 cycles per value),  $n = 24$ .

**vrs4\_sinf: Four-valued single precision Sine**`__m128 __vrs4_sinf (__m128 x)`

C Prototype:

`__m128 __vrs4_sinf(__m128 x);`

Inputs:

`__m128 x` - the four single precision inputs.

Outputs:

`__m128 y` - the four single precision Sine results, returned in `xmm0`.

Notes:

`__vrs4_sinf` computes the Sine function of four input arguments.

This routine accepts four single precision input values passed as a `__m128` value. The result is the single precision Sine of the four values, returned as a `__m128` value. This is a *relaxed* version of `sinf`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range. This routine may return slightly worse than 1 *ulp* for very large values between  $4e5$  and  $5e5$ .

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

176 cycles for most valid inputs  $< 5e5$  (44 cycles per value).

**vrsa\_sinf: Array single precision Sine**

```
void vrsa_sinf (int n, float *x, float *y)
```

C Prototype:

```
void vrsa_sinf (int n, float *x, float *y)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
float	*x	- pointer to the array of input values.
float	*y	- pointer to the array of output values.

Outputs:

Sine for each x value, filled into the y array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_SINF(N,X,Y)
```

Inputs:

INTEGER	N	- the number of values in both the input and output arrays.
REAL	X(N)	- array of single precision input values.

Outputs:

REAL	Y(N)	- array of Sines of input values.
------	------	-----------------------------------

Notes:

vrsa\_sinf computes the Sine function for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes  $\sin(x)$  for each input value, and stores the result in the array pointed to by the y pointer input. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of `sinf`, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

43 cycles per value for most valid inputs  $< 5e5$ ,  $n = 24$ .

**vr2\_sincos: Two-valued double precision Sine and Cosine**

```
void __vr2_sincos (__m128d x, __m128d* S, __m128d* C)
```

C Prototype:

```
void __vr2_sincos(__m128d x, __m128d* S, __m128d* C);
```

Inputs:

`__m128d x` - the double precision input value pair.

Outputs:

(Sine of `x` and Cosine of `x`.)

`__m128d *S` - Pointer to the double precision Sine result pair.

`__m128d *C` - Pointer to the double precision Cosine result pair.

Notes:

`__vr2_sincos` computes the Sine and Cosine functions of two input arguments.

This routine accepts a pair of double precision input values passed as a `__m128d` value. The result is the double precision Sin and Cosine of both values, returned as a `__m128d` value. This is a *relaxed* version of `sincos`, suitable for use with fastmath compiler flags or application

not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

Input	Output
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

154 cycles for most valid inputs < 5e5 (77 cycles per Sine and Cosine of a value).



**vrda\_sincos: Array double precision Sine and Cosine**

```
void vrda_sincos (int n, double *x, double *ys, double *yc)
```

C Prototype:

```
void vrda_sincos (int n, double *x, double *ys, double *yc)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
double	*x	- pointer to the array of input values.
double	*ys	- pointer to the array of sin output values.
double	*yc	- pointer to the array of cos output values.

Outputs:

Sine for each x value, filled into the ys array.

Cosine for each x value, filled into the yc array.

Fortran Subroutine Interface:

```
SUBROUTINE VRDA_SINCOS(N,X,YS,YC)
```

Inputs:

INTEGER N - the number of values in both the input and output arrays.

DOUBLE PRECISION X(N) - array of double precision input values.

Outputs:

DOUBLE PRECISION YS(N) - array of Sines of input values.

DOUBLE PRECISION YC(N) - array of Cosines of input values.

Notes:

vrda\_sincos computes the Sine and Cosine functions for each element of an array of input arguments.

This routine accepts an array of double precision input values, computes sincos(x) for each input value, and stores the results in the arrays pointed to by the ys and yc pointer inputs. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of sincos, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 2 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
QNaN	same QNaN
SNaN	same NaN converted to QNaN
$+\infty$	QNaN
$-\infty$	QNaN

Performance:

180 cycles for most valid inputs  $< 5e5$  (43 cycles per Sin and Cos of a value),  $n = 24$ .

**vrs4\_sincosf: Four-valued single precision Sine and Cosine**

```
void __vrs4_sincosf (__m128 x, __m128* S, __m128* C)
```

C Prototype:

```
void __vrs4_sincosf(__m128 x, __m128* S, __m128* C);
```

Inputs:

\_\_m128 x - the single precision input value pair.

Outputs:

(Sine of x and Cosine of x.)

\_\_m128 \*S - Pointer to the single precision Sine result pair.

\_\_m128 \*C - Pointer to the single precision Cosine result pair.

Notes:

\_\_vrs4\_sincosf computes the Sine and Cosine functions of four input arguments.

This routine accepts four single precision input values passed as a \_\_m128 value. The result is the single precision Sin and Cosine of all four values, returned as a \_\_m128 value. This is a *relaxed* version of sincosf, suitable for use with fastmath compiler flags or application

not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

<b>Input</b>	<b>Output</b>
<i>QNaN</i>	same <i>QNaN</i>
<i>SNaN</i>	same <i>NaN</i> converted to <i>QNaN</i>
$+\infty$	<i>QNaN</i>
$-\infty$	<i>QNaN</i>

Performance:

220 cycles for most valid inputs < 5e5 (55 cycles per Sine and Cosine of a value).

**vrsa\_sincosf: Array single precision Sine and Cosine**

```
void vrsa_sincosf (int n, float *x, float *ys, float *yc)
```

C Prototype:

```
void vrsa_sincosf (int n, float *x, float *ys, float *yc)
```

Inputs:

int	n	- the number of values in both the input and output arrays.
float	*x	- pointer to the array of input values.
float	*ys	- pointer to the array of sin output values.
float	*yc	- pointer to the array of cos output values.

Outputs:

Sine for each x value, filled into the ys array.

Cosine for each x value, filled into the yc array.

Fortran Subroutine Interface:

```
SUBROUTINE VRSA_SINCOSF(N,X,YS,YC)
```

Inputs:

INTEGER N - the number of values in both the input and output arrays.

REAL X(N) - array of single precision input values.

Outputs:

REAL YS(N) - array of Sines of input values.

REAL YC(N) - array of Cosines of input values.

Notes:

vrsa\_sincosf computes the Sine and Cosine functions for each element of an array of input arguments.

This routine accepts an array of single precision input values, computes sincos(x) for each input value, and stores the results in the arrays pointed to by the ys and yc pointer inputs. It is the responsibility of the calling program to allocate/deallocate enough storage for the output array. This is a *relaxed* version of sincos, suitable for use with fastmath compiler flags or applications not requiring full error handling. Denormal inputs may produce unpredictable results. Special case inputs produce C99 return values. The routine is accurate to better than 1 *ulp* over the valid input range.

Special case return values:

Input	Output
QNaN	same QNaN
SNaN	same NaN converted to QNaN
$+\infty$	QNaN
$-\infty$	QNaN

Performance:

53 cycles per value for most valid inputs  $< 5e5$ ,  $n = 24$ .

## 8 References

- [1] C.L. Lawson, R.J. Hanson, D. Kincaid, and F.T. Krogh, *Basic linear algebra subprograms for Fortran usage*, ACM Trans. Maths. Soft., 5 (1979), pp. 308–323.
- [2] J.J. Dongarra, J. Du Croz, S. Hammarling, and R.J. Hanson, *An extended set of FORTRAN basic linear algebra subroutines*, ACM Trans. Math. Soft., 14 (1988), pp. 1–17.
- [3] J.J. Dongarra, J. Du Croz, I.S. Duff, and S. Hammarling, *A set of level 3 basic linear algebra subprograms*, ACM Trans. Math. Soft., 16 (1990), pp. 1–17.
- [4] David S. Dodson, Roger G. Grimes, John G. Lewis, *Sparse Extensions to the FORTRAN Basic Linear Algebra Subprograms*, ACM Trans. Math. Soft., 17 (1991), pp. 253–263.
- [5] E. Anderson, Z. Bai, C. Bischof, S. Blackford, J. Demmel, J. Dongarra, J. Du Croz, A. Greenbaum, S. Hammarling, A. McKenney, and D. Sorensen, *LAPACK User's Guide*, SIAM, Philadelphia, (1999).
- [6] D. E. Knuth, *The Art of Computer Programming* Addison-Wesley, 1997.
- [7] J. Banks, *Handbook on Simulation*, Wiley, 1998.
- [8] A. Menezes, P. van Oorschot, and S. Vanstone, *Handbook of Applied Cryptography*, Chapter 5, CRC Press, 1996.
- [9] Chapter Introduction G05 - Random Number Generators *The NAG Fortran Library Manual, Mark 21* Numerical Algorithms Group, 2005.
- [10] N. M. MacLaren, The generation of multiple independent sequences of pseudorandom numbers, *Appl. Statist.*, 1989, 38, 351–359.
- [11] M. Matsumoto and T. Nishimura, Mersenne twister: A 623-dimensionally equidistributed uniform pseudorandom number generator, *ACM Transactions on Modelling and Computer Simulations*, 1998.
- [12] P. L'Ecuyer, Good parameter sets for combined multiple recursive random number generators, *Operations Research*, 1999, 47, 159–164.
- [13] Programming languages - C - ISO/IEC 9899:1999
- [14] IEEE Standard for Binary Floating-Point Arithmetic (ANSI/IEEE Std 754-1985)
- [15] P. L'Ecuyer and R. Simard, *TestU01: A Software Library in ANSI C for Empirical Testing of Random Number Generators*, Departement d'Informatique et de Recherche Operationnelle, Universite de Montreal, 2002. Software and user's guide available at <http://www.iro.umontreal.ca/~lecuyer>

# Subject Index

## 2

2D FFT..... 40

## 3

3D FFT..... 49

## A

accessing ACML (Compaq Visual Fortran under  
32-bit Windows)..... 10  
accessing ACML (GNU g77/gcc under 32-bit  
Windows)..... 8  
accessing ACML (GNU g77/gcc under Linux)... 5  
accessing ACML (GNU gfortran/gcc under Linux)  
..... 6  
accessing ACML (Intel Fortran/Microsoft C under  
32-bit Windows)..... 10  
accessing ACML (Linux)..... 5  
accessing ACML (other compilers under Linux).. 8  
accessing ACML (PathScale pathf90/pathcc under  
Linux)..... 7  
accessing ACML (PGI pgf77/pgf90/pgcc or  
Microsoft C under 64-bit Windows)..... 11  
accessing ACML (PGI pgf77/pgf90/pgcc under  
32-bit Windows)..... 9  
accessing ACML (PGI pgf77/pgf90/pgcc under  
Linux)..... 6  
accessing ACML (Salford ftn95 under 32-bit  
Windows)..... 11  
accessing ACML (Solaris)..... 12  
accessing ACML (Sun f95/cc under Solaris)... 12  
accessing ACML under Windows..... 8  
accessing the base generators..... 71  
ACML C Interfaces..... 13  
ACML FORTRAN interfaces..... 13  
ACML installation test..... 15  
ACML version information..... 14  
ACML\_MV (ACML vector math functions)... 154  
ACML\_MV types..... 155

## B

base generator..... 65  
base generator, basic NAG generator..... 72  
base generator, blum-blum-shub..... 74  
base generator, calling..... 71  
base generator, definition..... 65  
base generator, initialization..... 66  
base generator, L'Ecuyer's combined recursive  
generator..... 74  
base generator, Mersenne twister..... 73  
base generator, recommendation..... 65  
base generator, user supplied..... 75

base generator, Wichmann-Hill..... 73  
basic NAG base generator..... 72  
beta distribution..... 87  
binomial distribution..... 115  
binomial distribution, using reference vector.. 129  
BLAS..... 16  
blum-blum-shub generator..... 74  
BRNG, definition..... 65

## C

C interfaces in ACML..... 13  
calling the base generators..... 71  
cauchy distribution..... 89  
chi-squared distribution..... 91  
complex FFT..... 21  
continuous multivariate distribution, gaussian  
..... 139  
continuous multivariate distribution, gaussian,  
using reference vector..... 144  
continuous multivariate distribution, normal.. 139  
continuous multivariate distribution, normal, using  
reference vector..... 144  
continuous multivariate distribution, students t  
..... 141  
continuous multivariate distribution, students t,  
using reference vector..... 146  
continuous univariate distribution, beta..... 87  
continuous univariate distribution, cauchy..... 89  
continuous univariate distribution, chi-squared  
..... 91  
continuous univariate distribution, exponential  
..... 93  
continuous univariate distribution, f..... 95  
continuous univariate distribution, fisher's variance  
ratio distribution..... 95  
continuous univariate distribution, gamma..... 97  
continuous univariate distribution, gaussian.... 99  
continuous univariate distribution, logistic.... 101  
continuous univariate distribution, lognormal.. 103  
continuous univariate distribution, normal..... 99  
continuous univariate distribution, students t.. 105  
continuous univariate distribution, t..... 105  
continuous univariate distribution, triangular.. 107  
continuous univariate distribution, uniform... 109  
continuous univariate distribution, von mises.. 111  
continuous univariate distribution, weibull.... 113  
copying a generator..... 66  
cryptologically secure, definition..... 65  
cryptologically secure, generator..... 74

**D**

- determining the best ACML version for your system ..... 3
- discrete multivariate distribution, multinomial ..... 152
- discrete univariate distribution, binomial ..... 115
- discrete univariate distribution, binomial, using reference vector ..... 129
- discrete univariate distribution, geometric ..... 117
- discrete univariate distribution, geometric, using reference vector ..... 131
- discrete univariate distribution, hypergeometric ..... 119
- discrete univariate distribution, hypergeometric, using reference vector ..... 133
- discrete univariate distribution, negative binomial ..... 121
- discrete univariate distribution, negative binomial, using reference vector ..... 135
- discrete univariate distribution, poisson ..... 123
- discrete univariate distribution, poisson, using reference vector ..... 137
- discrete univariate distribution, uniform ..... 125
- distribution generator, definition ..... 65

**E**

- example programs ..... 15
- exponential distribution ..... 93

**F**

- f distribution ..... 95
- fast basic math functions ..... 156
- Fast Fourier Transforms ..... 21
- feedback shift generator ..... 73
- FFT ..... 21
- FFT efficiency ..... 22
- FFT of multiple complex sequences ..... 31
- FFT of multiple Hermitian sequences ..... 63
- FFT of multiple real sequences ..... 59
- FFT of single complex sequence ..... 24
- FFT of single Hermitian sequence ..... 61
- FFT of single real sequence ..... 57
- FFT plan ..... 23
- fisher's variance ratio distribution ..... 95
- FORTTRAN interfaces in ACML ..... 13

**G**

- gamma distribution ..... 97
- gaussian distribution (multivariate) ..... 139
- gaussian distribution (univariate) ..... 99
- gaussian distribution, multivariate, using reference vector ..... 144
- general information ..... 3
- generalized feedback shift generator ..... 73

- generating discrete variates from a reference vector ..... 127
- geometric distribution ..... 117
- geometric distribution, using reference vector .. 131

**H**

- Hermitian data sequences (FFT) ..... 56
- hypergeometric distribution ..... 119
- hypergeometric distribution, using reference vector ..... 133

**I**

- initialization of a generator ..... 66
- installation test ..... 15
- introduction ..... 1

**L**

- L'Ecuyer's combined recursive generator ..... 74
- language interfaces ..... 13
- LAPACK ..... 17
- LAPACK blocking factors ..... 18
- LAPACK reference sources ..... 17
- libm names ..... 154
- library manual ..... 15
- library version information ..... 14
- linear congruential generator, basic NAG generator ..... 72
- linear congruential generator, Wichmann-Hill .. 73
- linking with ACML ..... 3
- linking with Linux ACML ..... 5
- linking with Solaris ACML ..... 12
- linking with Windows ACML ..... 8
- logistic distribution ..... 101
- lognormal distribution ..... 103

**M**

- Mersenne twister ..... 73
- Mersenne twister, multiple streams ..... 80
- multinomial distribution ..... 152
- multiple recursive generator, L'Ecuyer's combined recursive generator ..... 74
- multiple streams ..... 79
- multiple streams, block splitting ..... 80
- multiple streams, L'Ecuyer's combined recursive generator ..... 80, 83
- multiple streams, leap frogging ..... 83
- multiple streams, Mersenne twister ..... 80
- multiple streams, NAG basic generator ..... 80, 83
- multiple streams, skip ahead ..... 80
- multiple streams, using different generators ..... 80
- multiple streams, using different seeds ..... 80
- multiple streams, Wichmann-Hill generator ... 80, 83
- multivariate distribution, gaussian ..... 139



multivariate distribution, gaussian, using reference vector ..... 144  
 multivariate distribution, multinomial ..... 152  
 multivariate distribution, normal ..... 139  
 multivariate distribution, normal, using reference vector ..... 144  
 multivariate distribution, students t ..... 141  
 multivariate distribution, students t, using reference vector ..... 146

## N

negative binomial distribution ..... 121  
 negative binomial distribution, using reference vector ..... 135  
 normal distribution (multivariate) ..... 139  
 normal distribution (univariate) ..... 99  
 normal distribution, multivariate, using reference vector ..... 144

## P

period of a random number generator, definition ..... 65  
 plan, default, FFTs ..... 23  
 plan, generated, FFTs ..... 23  
 poisson distribution ..... 123  
 poisson distribution, using reference vector ... 137  
 PRNG, definition ..... 65  
 pseudo-random number, definition ..... 65

## Q

QRNG, definition ..... 65  
 quasi-random number, definition ..... 65

## R

random bit stream ..... 71  
 real data sequences (FFT) ..... 56  
 real FFT ..... 56  
 reference vector, binomial distribution ..... 129  
 reference vector, gaussian (multivariate) ..... 148  
 reference vector, generating discrete variates from ..... 127  
 reference vector, geometric distribution ..... 131  
 reference vector, hypergeometric distribution .. 133  
 reference vector, negative binomial distribution ..... 135  
 reference vector, normal (multivariate) ..... 148  
 reference vector, poisson distribution ..... 137  
 reference vector, students t (multivariate) ..... 150  
 retrieving the state of a generator ..... 66

## S

saving the state of a generator ..... 66  
 seed, definition ..... 65  
 sparse BLAS ..... 16

students t distribution ..... 105  
 students t distribution (multivariate) ..... 141  
 students t distribution, multivariate, using reference vector ..... 146

## T

t distribution ..... 105  
 triangular distribution ..... 107

## U

uniform distribution (continuous) ..... 109  
 uniform distribution (discrete) ..... 125  
 univariate distribution, beta ..... 87  
 univariate distribution, binomial ..... 115  
 univariate distribution, binomial, using reference vector ..... 129  
 univariate distribution, cauchy ..... 89  
 univariate distribution, chi-squared ..... 91  
 univariate distribution, exponential ..... 93  
 univariate distribution, f ..... 95  
 univariate distribution, fisher's variance ratio .. 95  
 univariate distribution, gamma ..... 97, 99  
 univariate distribution, geometric ..... 117  
 univariate distribution, geometric, using reference vector ..... 131  
 univariate distribution, hypergeometric ..... 119  
 univariate distribution, hypergeometric, using reference vector ..... 133  
 univariate distribution, logistic ..... 101  
 univariate distribution, lognormal ..... 103  
 univariate distribution, negative binomial ..... 121  
 univariate distribution, negative binomial, using reference vector ..... 135  
 univariate distribution, normal ..... 99  
 univariate distribution, poisson ..... 123  
 univariate distribution, poisson, using reference vector ..... 137  
 univariate distribution, students t ..... 105  
 univariate distribution, t ..... 105  
 univariate distribution, triangular ..... 107  
 univariate distribution, uniform (continuous) .. 109  
 univariate distribution, uniform (discrete) .... 125  
 univariate distribution, von mises ..... 111  
 univariate distribution, weibull ..... 113  
 user supplied generators ..... 75

## V

vector math functions ..... 172  
 von mises distribution ..... 111

## W

weak aliases ..... 154  
 weibull distribution ..... 113  
 Wichmann-Hill base generator ..... 73  
 Wichmann-Hill, multiple streams ..... 80

# Routine Index

—	
__vrd2_cos	172
__vrd2_exp	177
__vrd2_log	183
__vrd2_log10	190
__vrd2_sin	204
__vrd2_sincos	209
__vrd4_cos	173
__vrd4_exp	178
__vrd4_log	184
__vrd4_log10	191
__vrd4_sin	205
__vrs4_cosf	175
__vrs4_expf	180
__vrs4_log10f	195
__vrs4_logf	187
__vrs4_powf	200
__vrs4_powxf	202
__vrs4_sincosf	212
__vrs4_sinf	207
__vrs8_expf	181
__vrs8_log10f	196
__vrs8_logf	188

## A

acmlinfo	14
ACMLINFO	14
acmlversion	14
ACMLVERSION	14

## C

CFFT1D	26
CFFT1DX	29
CFFT1M	34
CFFT1MX	38
CFFT2D	42
CFFT2DX	46
CFFT3D	51
CFFT3DX	54
CSFFT	62
CSFFTM	64

## D

DRANDBETA	87
DRANDBINOMIAL	115
DRANDBINOMIALREFERENCE	129
DRANDBLUMBLUMSHUB	72
DRANDCAUCHY	89
DRANDCHISQUARED	91
DRANDDISCRETEUNIFORM	125
DRANDEXPONENTIAL	93

DRANDF	95
DRANDGAMMA	97
DRANDGAUSSIAN	99
DRANDGENERALDISCRETE	127
DRANDGEOMETRIC	117
DRANDGEOMETRICREFERENCE	131
DRANDHYPERGEOMETRIC	119
DRANDHYPERGEOMETRICREFERENCE	133
DRANDINITIALIZE	67
DRANDINITIALIZEBBS	70
DRANDINITIALIZEUSER	76
DRANDLEAPFROG	85
DRANDLOGISTIC	101
DRANDLOGNORMAL	103
DRANDMULTINOMIAL	152
DRANDMULTINORMAL	139
DRANDMULTINORMALR	144
DRANDMULTINORMALREFERNCE	148
DRANDMULTISTUDENTSREFERENCE	150
DRANDMULTISTUDENTST	141
DRANDMULTISTUDENTSTR	146
DRANDNEGATIVEBINOMIAL	121
DRANDNEGATIVEBINOMIALREFERENCE	135
DRANDPOISSON	123
DRANDPOISSONREFERENCE	137
DRANDSKIPAHHEAD	82
DRANDSTUDENTST	105
DRANDTRIANGULAR	107
DRANDUNIFORM	109
DRANDVONMISES	111
DRANDWEIBULL	113
DZFFT	57
DZFFTM	59

## F

fastcos	156
fastcosf	157
fastexp	158
fastexpf	159
fastlog	160
fastlog10	162
fastlog10f	163
fastlogf	161
fastpow	164
fastpowf	166
fastsin	168
fastsincos	170
fastsincosf	171
fastsinf	169

## I

ILAENVSET	18
-----------	----

## S

SCFFT .....	58
SCFFTM .....	60
SRANDBINOMIALREFERENCE .....	129
SRANDCHISQUARED .....	91
SRANDGEOMETRICREFERENCE .....	131
SRANDBETA .....	87
SRANDBINOMIAL .....	115
SRANDBLUMBLUMSHUB .....	72
SRANDCAUCHY .....	89
SRANDDISCRETEUNIFORM .....	125
SRANDEXPONENTIAL .....	93
SRANDF .....	95
SRANDGAMMA .....	97
SRANDGAUSSIAN .....	99
SRANDGENERALDISCRETE .....	127
SRANDGEOMETRIC .....	117
SRANDHYPERGEOMETRIC .....	119
SRANDHYPERGEOMETRICREFERENCE .....	133
SRANDINITIALIZE .....	67
SRANDINITIALIZEBBS .....	70
SRANDINITIALIZEUSER .....	76
SRANDLEAPFROG .....	85
SRANDLOGISTIC .....	101
SRANDLOGNORMAL .....	103
SRANDMULTINOMIAL .....	152
SRANDMULTINORMAL .....	139
SRANDMULTINORMALR .....	144
SRANDMULTINORMALREFERENCE .....	148
SRANDMULTISTUDENTST .....	141
SRANDMULTISTUDENTSTR .....	146
SRANDMULTISTUDENTSTREFERENCE .....	150
SRANDNEGATIVEBINOMIAL .....	121
SRANDNEGATIVEBINOMIALREFERENCE .....	135
SRANDPOISSON .....	123
SRANDPOISSONREFERENCE .....	137
SRANDSKIPHEAD .....	82

SRANDSTUDENTST .....	105
SRANDTRIANGULAR .....	107
SRANDUNIFORM .....	109
SRANDVONMISES .....	111
SRANDWEIBULL .....	113

## U

UGEN .....	79
UINI .....	78

## V

vrda_cos .....	174
vrda_exp .....	179
vrda_log .....	185
vrda_log10 .....	193
vrda_sin .....	206
vrda_sincos .....	210
vrda_cosf .....	176
vrda_expf .....	182
vrda_log10f .....	198
vrda_logf .....	189
vrda_sincosf .....	213
vrda_sinf .....	208

## Z

ZDFFT .....	61
ZDFFTM .....	63
ZFFT1D .....	25
ZFFT1DX .....	27
ZFFT1M .....	32
ZFFT1MX .....	36
ZFFT2D .....	41
ZFFT2DX .....	43
ZFFT3D .....	50
ZFFT3DX .....	52